

Autodesk® MotionBuilder® 2011

Installation and Licensing Guide



© 2010 Autodesk, Inc. All rights reserved.

Except as otherwise permitted by Autodesk, Inc., this publication, or parts thereof, may not be reproduced in any form, by any method, for any purpose.

Certain materials included in this publication are reprinted with the permission of the copyright holder.

The following are registered trademarks or trademarks of Autodesk, Inc., and/or its subsidiaries and/or affiliates in the USA and other countries: 3DEC (design/logo), 3December, 3December.com, 3ds Max, Algor, Alias, Alias (swirl design/logo), AliasStudio, AliasWavefront (design/logo), ATC, AUGI, AutoCAD, AutoCAD Learning Assistance, AutoCAD LT, AutoCAD Simulator, AutoCAD SQL Extension, AutoCAD SQL Interface, Autodesk, Autodesk Envision, Autodesk Intent, Autodesk Inventor, Autodesk Map, Autodesk MapGuide, Autodesk Streamline, AutoLISP, AutoSnap, AutoSketch, AutoTrack, Backburner, Backdraft, Built with ObjectARX (logo), Burn, Buzzsaw, CAiCE, Civil 3D, Cleaner, Cleaner Central, ClearScale, Colour Warper, Combustion, Communication Specification, Constructware, Content Explorer, Dancing Baby (image), DesignCenter, Design Doctor, Designer's Toolkit, DesignKids, DesignProf, DesignServer, DesignStudio, Design Web Format, Discreet, DWF, DWG, DWG (logo), DWG Extreme, DWG TrueConvert, DWG TrueView, DXF, Ecotect, Exposure, Extending the Design Team, Face Robot, FBX, Fempro, Fire, Flame, Flare, Flint, FMDesktop, Freewheel, GDX Driver, Green Building Studio, Heads-up Design, Heidi, HumanIK, IDEA Server, i-drop, ImageModeler, iMOUT, Incinerator, Inferno, Inventor, Inventor LT, Kaydara, Kaydara (design/logo), Kynapse, Kynogon, LandXplorer, Lustre, MatchMover, Maya, Mechanical Desktop, Moldflow, Moonbox, MotionBuilder, Movimento, MPA, MPA (design/logo), Moldflow Plastics Advisers, MPI, Moldflow Plastics Insight, MPX, MPX (design/logo), Moldflow Plastics Xpert, Mudbox, Multi-Master Editing, Navisworks, ObjectARX, ObjectDBX, Open Reality, Opticore, Opticore Opus, Pipeplus, PolarSnap, PortfolioWall, Powered with Autodesk Technology, Productstream, ProjectPoint, ProMaterials, RasterDWG, RealDWG, Real-time Roto, Recognize, Render Queue, Retimer, Reveal, Revit, Showcase, ShowMotion, SketchBook, Smoke, Softimage, SoftimageXSI (design/logo), Sparks, SteeringWheels, Stitcher, Stone, StudioTools, ToolClip, Topobase, Toxik, TrustedDWG, ViewCube, Visual, Visual LISP, Volo, Vtour, Wire, Wiretap, WiretapCentral, XSI, and XSI (design/logo).

Python and the Python logo are trademarks or registered trademarks of the Python Software Foundation.

ACE™, TAO™, CIAO™, and CoSMIC™ are copyrighted by Douglas C. Schmidt and his research group at Washington University, University of California, Irvine, and Vanderbilt University, Copyright (c) 1993-2009, all rights reserved.

All other brand names, product names or trademarks belong to their respective holders.

Disclaimer

THIS PUBLICATION AND THE INFORMATION CONTAINED HEREIN IS MADE AVAILABLE BY AUTODESK, INC. "AS IS." AUTODESK, INC. DISCLAIMS ALL WARRANTIES, EITHER EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE REGARDING THESE MATERIALS.

Published by: Autodesk, Inc.

111 McInnis Parkway

San Rafael, CA 94903, USA

Document Title: Autodesk MotionBuilder 2011 Installation and Licensing Guide

Date: 1 April 2010

Document Version: 2010.04.01.02

Build Version: 2010.04.01.02

Contents

	MotionBuilder Installation Guide	1
Chapter 1	MotionBuilder Installation	3
	Introduction	3
	Prepare to Install MotionBuilder	4
	Verify the system requirements	4
	Verify the certified hardware	4
	Locate your serial number and product key	4
	Understand your license type	5
	Close all running programs	5
	Install and Run the Product	6
	Install MotionBuilder	6
	Troubleshoot Installation	11
	General installation issues	11
	Networking issues	14
	Uninstall and Maintenance Issues	14
Chapter 2	Glossary of Installation Terms	17
	Acronyms	17
	MSI	17
	MSP	17
	Terms	17
	activate	18

Active Directory	18
directory service	18
FLEXnet	18
License Transfer utility	18
multi-seat stand-alone installation	18
network license installation	19
partial profile	19
patch	19
power user	19
pull technology	19
scripting	19
service pack	19
silent mode	20

Autodesk Licensing Guide 21

Chapter 3 Stand-Alone Licensing Guide 23

Stand-Alone Licensing	23
Introduction	23
Multi-Seat Stand-Alone License	23
Activate Your Product	24
Manage your Stand-Alone License	24
Check Product Information	24
View Product Information	25
Save License Information as a Text File	25
Update your Serial Number	25
Transfer your Stand-Alone License	26
About the License Transfer Utility	27
Install the Autodesk Product	28
Export a License	28
Import a License	29
Troubleshoot a Stand-Alone License Error	30
Hardware Changes	30
Reinstalling an Operating System	31
Changing the System Date and Time	31

Chapter 4 Network Licensing Guide 33

Network Licensing	33
Plan Your Network Licensing	33
System Requirements for the Network License Manager (Windows)	33
Plan Your License Server Configuration	35
Learn About Your License	37
Network License Manager	51

	Install the Network License Manager	51
	Patch the License Manager on an IPv6 Network	52
	Obtain a License Through autodesk.com	53
	Obtain the Server Host Name and Host ID Manually	53
	Configure a License Server	54
	Uninstall the Network License Manager	56
	Network Licensing Tools	56
	FLEXnet Configuration Tools	57
	License Borrowing	61
	Network Licensing FAQs	63
Chapter 5	Glossary of Licensing Terms	67
	Acronyms	67
	IPv6	67
	JRE (Java Runtime Environment)	67
	Terms	67
	ADSKFLEX_LICENSE_FILE	68
	adskflex.exe	68
	borrowed license	68
	daemon	68
	debug log file	68
	distributed server	68
	Ethernet address	69
	feature code	69
	FLEXnet	69
	heartbeat signal	69
	host ID	69
	host name	69
	idle	69
	license file	70
	license server	70
	license timeout	70
	licpath.lic	70
	lmgrd.exe	70
	lmtools.exe	70
	lmutil.exe	70
	master daemon	71
	network license	71
	network license installation	71
	Network License Manager	71
	Options file	71
	physical address	71
	redundant server	71
	report log file	72
	single server	72
	stand-alone license	72

vendor daemon72
workstation72
Index73

MotionBuilder Installation Guide

MotionBuilder Installation

1

Welcome to the Autodesk MotionBuilder 2011® for Microsoft® Windows® software product. This chapter provides all the information required to install the MotionBuilder software product as well as all the procedures required to perform prior installing the software product.

For last minute updates to the Autodesk MotionBuilder 2011 software product and documentation, refer to the *Autodesk MotionBuilder 2011 Release Notes* posted to the Autodesk MotionBuilder Product Documentation page at:

<http://www.autodesk.com/motionbuilder2011-documentation>. You can download (from this web site) all the latest updates to the MotionBuilder documentation.

NOTE Information in the *Autodesk MotionBuilder 2011 Release Notes* pertaining to the installation and licensing of the MotionBuilder software product supersede information pertaining to the installation and licensing in the *Autodesk MotionBuilder 2011 Installation and Licensing Guide*.

Introduction

The steps to install the MotionBuilder software product on a single computer with a stand-alone license, or on many client computers that will access a network license from a server machine are similar. The basic workflow to install MotionBuilder is as follows:

- 1 [Prepare to Install MotionBuilder](#) on page 4
- 2 [Install MotionBuilder](#) on page 6

NOTE If you will use a network license to run MotionBuilder, contact your network administrator to find your license server name before you start the installation. If you will use a stand-alone license to run MotionBuilder, see *Activate your Product* for information on obtaining your stand-alone license.

Prepare to Install MotionBuilder

Before you install MotionBuilder, ensure you do the following:

- [Verify the system requirements](#) on page 4
See <http://www.autodesk.com/motionbuilder-systemrequirements>
- [Verify the certified hardware](#) on page 4
See <http://www.autodesk.com/motionbuilder-hardware>
- [Locate your serial number and product key](#) on page 4
If you have not yet purchased a MotionBuilder license, follow the online installation instructions.
- [Understand your license type](#) on page 5
- [Close all running programs](#) on page 5

Verify the system requirements

Ensure you have the minimum system requirements for running the 32-bit / 64-bit version of the MotionBuilder software product by going to: <http://www.autodesk.com/motionbuilder-systemrequirements>.

Verify the certified hardware

Verify your hardware is certified to run the 32-bit / 64-bit version of the MotionBuilder software product by going to: <http://www.autodesk.com/motionbuilder-hardware>. If you want to purchase hardware that is certified by Autodesk to optimally run the MotionBuilder software product, choose from the hardware configurations provided on this web page.

Locate your serial number and product key

To install MotionBuilder, you need a serial number and a product key. If you have already purchased a MotionBuilder license, your product serial number and product key can be found on the outside of the product packaging or in the *Autodesk Upgrade and Licensing Information* email you received if you downloaded your product. Make sure to have these available before you install the program so that you don't have to stop in the middle of the installation.

NOTE If you have lost your serial number or product key, contact the Autodesk Business Center (ABC) at 800-538-6401 for assistance.

The serial number must contain a three-digit prefix followed by an eight-digit number. The product key consists of five characters.

The information you enter is permanently retained with the product. Because you can't change this information later without uninstalling, take care when entering the information. To review this product information later, in MotionBuilder, under the Help menu, click About MotionBuilder. In the About box, click Product License Information.

NOTE You may enter your product information at any time during your trial mode period if you opt to install the product in that mode.

Understand your license type

During the installation process, you need to select which type of license you will use to run MotionBuilder: a stand-alone license or a network license.

A [stand-alone license](#) on page 72 (sometimes referred to as a node-locked license) is a license for a single computer. The stand-alone license enables you to run the MotionBuilder product only on the computer where the license is installed.

A [network license](#) on page 71 (sometimes referred to as a floating license) is a license that can be shared by various computers on a network. The MotionBuilder product is installed on many computers (sometimes referred to as clients), each with a license file that accesses the network license server.

If you plan to use a stand-alone license to run MotionBuilder, you enter your serial number during the installation, then register and activate the license after launching the product. See [Activate your product](#).

If you plan to use a network license, you need to enter the name of your license server during the installation. Obtain the license server name from your network administrator before you start the installation process.

If you are setting up a MotionBuilder license server, refer to the [Network Licensing Guide](#) on setting up a MotionBuilder license server.

Close all running programs

The MotionBuilder installation process may stop if some applications such as Microsoft® Outlook® or virus-checking programs are running. To avoid any

licensing conflicts when installing MotionBuilder, it is important that you close all programs and disable virus detection software before launching the installer.

Install and Run the Product

To use the product, you must install the product, register and activate it, and then launch it. You must have administrative permissions to install MotionBuilder.

This section provides instructions for installing and activating MotionBuilder for an individual user on a stand-alone computer. For information about installing network-licensed or multi-seat stand-alone versions of the program, see [Network Licensing Guide](#) on page 33.

Install MotionBuilder


The MotionBuilder Installation wizard contains all installation-related material in one place. From the installation wizard, you can access user documentation, change the installer language, select a language for your product, install supplemental tools, and add online support services.

- **Review the installation documentation.** It is recommended that you take the time to familiarize yourself with the complete installation process before you install MotionBuilder. You can access information on installation from the installation wizard by selecting the *Read this Documentation* option, the *Documentation* and information links, or through the Help system. For late-breaking information, it is also recommended that you review the product *Readme*.

To install MotionBuilder using default values on a stand-alone computer:

- 1 Do one of the following to start the MotionBuilder Installation wizard:
 - If you are installing MotionBuilder from a DVD, insert the DVD into your DVD-ROM drive.
If the installation process does not start automatically, double-click the *autorun.exe* file on your DVD drive.
 - If you are installing MotionBuilder from a download package, double-click the *Autodesk_MotionBuilder_2011_English_Win_32-64bit.exe* file you downloaded.

- 2 On the initial page, click Install Products.
- 3 On the Select the Products to Install page, select your product(s). Click Next.
- 4 Review the Autodesk software license agreement. Click I Accept, and then click Next.
- 5 On the User and Product Information page, enter your user information, serial number, and product key. Click Next.



The screenshot shows a form titled "User and Product Information" with the following fields and options:

- First name: MyFirstName
- Last name: MyLastName
- Organization: MyOrganization
- Radio buttons:
 - I want to try this product for 30 days
 - I have my product information
- Serial number: 123 - 12345678
- Product key: 12345

WARNING After you click Next, you cannot change the information entered on this page unless you uninstall the product.

- 6 On the Begin Installation page, click Install. In the configuration warning message, click Yes.
- 7 On the Installation Complete page, you can view the installation log and the MotionBuilder *Readme*.
- 8 Click Finish.

You have successfully installed MotionBuilder. You are now ready to register your product and start using the program. To register the product, start MotionBuilder and follow the on-screen instructions.

To install MotionBuilder using Custom settings on a stand-alone computer:

- 1 Do one of the following to start the MotionBuilder Installation wizard:
 - If you are installing MotionBuilder from a DVD, insert the DVD into your DVD-ROM drive.
 - If you are installing MotionBuilder from a download package, double-click the *Autodesk_MotionBuilder_2011_English_Win_32-64bit.exe* file you downloaded.
- 2 On the initial page, click Install Products.
- 3 On the Select the Products to Install page, select your product(s). Click Next.
- 4 Review the Autodesk software license agreement. Click I Accept, and then click Next.
- 5 On the User and Product Information page, enter your user information, serial number, and product key. Click Next.

WARNING After you click Next, you cannot change the information entered on this page unless you uninstall the product.

- 6 On the Begin Installation page, click Configure.

A window appears with tabs for each component you selected to install. Each tab gives you a wizard for configuring additional installation options. Select the tab for any component you want to change, then follow the instructions to complete the configuration.
- 7 On the Select the License Type page, select the license type (Stand-alone or Network). You can also elect to change the default product installation path.

NOTE If you select the Network license type, enter your license server name in the field that appears. Contact your network administrator to find the name of your license server.

- 8 Click another product tab to configure another product, or click Next and then Configuration Complete to return to the Begin Installation page. Click Install.

NOTE To retain a copy of your configuration settings, click Copy to Clipboard.

- 9 On the Installation Complete page, you can view the installation log or the MotionBuilder *Readme*.
- 10 Click Finish.

You have successfully installed MotionBuilder. You are now ready to register your product and start using the program. To register the product, start MotionBuilder and follow the on-screen instructions.

Install multiple or bundled products

Some Autodesk packages are comprised of multiple products or are part of multi-product bundles.

In the installation wizard, for packages containing multiple products, you can choose which products and languages you want to install. During the install process, you are informed whether a copy of the software is already installed. You are also warned if your system does not meet the minimum system requirements for the product. Each product name is displayed on its own tabbed panel; you can configure them individually.

If you purchased a package that is a multi-product bundle, such as an educational or institutional package, you may have a package that includes several Autodesk products. For these bundled packages, an Installer disc contains information for all the products in the package. The Installer disc helps you install all of the products.

Register and Activate MotionBuilder

The first time you start MotionBuilder, the Product License Activation wizard is displayed. You can either activate MotionBuilder at that time, or Try MotionBuilder and activate it later. Until you register and enter a valid activation code for MotionBuilder, you are operating the program in *trial mode* and the Product License Activation wizard is displayed for 30 days from the first time that you run the program.

If after 30 days of running MotionBuilder in trial mode you have not registered and provided a valid activation code, your only option is to register and activate MotionBuilder. You will not be able to run in trial mode after the 30 days expires. Once you register and activate MotionBuilder, the Product License Activation wizard is no longer displayed.

The fastest and most reliable way to register and activate your product is by using the Internet. Simply enter your registration information and send it to Autodesk over the Internet. Once you submit your information, registration and activation occur quickly.

To register and activate the product:

- 1 Click the Start menu ► Programs or All Programs ► Autodesk <Autodesk MotionBuilder> ► <Autodesk MotionBuilder>.
- 2 In the MotionBuilder Product License Activation wizard, select Activate, and then click Next.
This starts the activation process.
- 3 Click Register and Activate (Get an Activation Code).
- 4 Click Next and follow the on-screen instructions.

If you do not have Internet access, or if you want to use another method of registration, you can register and activate MotionBuilder in one of the following ways:

Email Create an email message with your registration information and send it to Autodesk.

Fax or Post/Mail Enter your registration information, and fax or mail the information to Autodesk.

Launch MotionBuilder

Assuming that you followed all of the previous steps outlined in this installation section, you can launch MotionBuilder and start taking advantage of its new and updated features. For more detailed information about the new features, learning videos, online Help, or MotionBuilder services and support, see the Welcome screen after you launch the product.

You can start MotionBuilder in the following ways:

- **Desktop shortcut icon.** When you install MotionBuilder, an MotionBuilder shortcut icon is placed on your desktop unless you cleared that option during installation. Double-click the MotionBuilder shortcut icon to start the program.
- **Start menu.** On the Start menu, click Programs or All Programs ► Autodesk ► <MotionBuilder> ► <MotionBuilder>.

- **Location where the MotionBuilder is installed.** You can run MotionBuilder in the location where you installed it.

Uninstall MotionBuilder

When you uninstall MotionBuilder, all components are removed. This means that even if you've previously added or removed components, or if you've reinstalled or repaired MotionBuilder, the uninstall removes all MotionBuilder installation files from your system.

You can uninstall the MotionBuilder software product via the Control Panel.

To uninstall MotionBuilder from a Windows XP® 32-bit / 64-bit system:

- 1 Go to Start > Settings > Control Panel.
- 2 On the Control Panel, double-click Add or Remove Programs.
- 3 On the Add Remove Programs dialog, select Autodesk MotionBuilder 2011 and click Change/Remove.

To uninstall MotionBuilder from a Windows 7 and Windows Vista 64-bit system:

- 1 Go to Start > Control Panel.
- 2 From the Control Panel, under Programs, select Uninstall a program.
- 3 In the Uninstall or change a program, select Autodesk MotionBuilder 2011 and click Uninstall.

Troubleshoot Installation

This section provides solutions to installation issues and answers to commonly asked questions that may arise while installing your product(s). Additional troubleshooting information and support is also available at <http://autodesk.com/servicesandsupport>

General installation issues

This section outlines common issues and their solutions that may arise while performing a general install of your product(s).

How can I check my graphics card driver to see if it needs to be updated?

It is recommended that you verify and update your graphics card driver to optimize your program. Use the following procedure to identify your current graphics card driver.

To identify your graphics card driver

- 1 On the Start menu (Windows), click Settings ► Control Panel.
- 2 Click the Display icon to access the Display Properties.
In Vista, click Settings ► Control Panel ► Personalization ► Display Settings.
- 3 Open the Settings tab and click the Advanced button.
- 4 Click the Adapter tab to check the adapter type.
- 5 Click the Properties button and open the Driver tab to check driver version and see if newer drivers are available.

TIP Many newer graphic cards offer tabbed pages where you can learn more precise information about your specific graphic card. If specific tab pages are present, refer to them instead of the Adapter tab.

What is the difference between a stand-alone license and a network license?

Stand-alone licensed products are registered and activated to an individual workstation. While the software can be installed on multiple systems in your facility, the license only allows one system to be operational. If you need to run more systems, you need to purchase more stand-alone licensed products, or consider converting to network licenses.

Network licensed products rely on the Network License Manager to keep track of software licenses. The software can be installed and run on multiple systems, up to the maximum number of licenses you've purchased. The Network License Manager "checks out" licenses until they are all in use. No further systems can run the program until a license is "checked in." If you need to run more systems, you can purchase additional licenses for the Network License Manager to maintain.

What is the benefit of using a network licensed version of the software?

Network licensed products are recommended for large production facilities, classrooms, and lab environments. The main advantage is that you can install products on more systems than the number of licenses you have purchased (for example, purchasing 25 licenses but installing on 40 workstations). At any one time, products will run on the maximum number of systems for which you have licenses. This means you get a true floating license. If software needs to be run on more systems, additional licenses can be purchased.

What features get installed during a Typical or Custom installation?

A typical installation includes all of the following features. If you choose a Custom installation, you can pick and choose from the following feature list.

Feature	Description
Open Reality® SDK and Python® Scripting Help	Open Reality SDK and Python Scripting Developer's Help and Reference Help
Samples	SDK sample files
MotionBuilder Help	MotionBuilder Help that includes a description of the new features and changes to the software, a list of resolved and unresolved bugs, tutorials, reference topics, workflow topics.
Learning Movies	Essential skills movies
License Transfer Utility	Utility that allows you to use an Autodesk product on more than one computer without purchasing an additional license for each computer. NOTE The utility will not be installed on unlocked versions of MotionBuilder.

How do I access my product documentation?

Learning and documentation material is available on the product media. The complete Help system is installed during the product installation process. During the installation process, you can access the Installation and Licensing Guide, the system requirements, and the certified hardware by selecting the Read the Documentation or Documentation links in the installation wizards.

Help files include user-interface help, workflows, tutorials, SDK developer's help, SDK and Python scripting reference Help. A *Readme* containing late-breaking information on the product is also available from the Installation Complete page.

Where can I check if service packs are available for my software?

To find out if a patch or Service Pack is available for your product, visit: <http://www.autodesk.com/motionbuilder-support>.

Networking issues

This section outlines common issues and their solutions with regards to performing a network installation or configuring your network license server(s).

Where do I find my server name?

When installing a network licensed product, you must specify the name of the server that will run the Network License Manager. If you don't know the server name, you can quickly find it by opening a Windows command prompt on the system that will be the Network License Manager. At the prompt, enter `ipconfig /all` and note the Host Name entry.

Uninstall and Maintenance Issues

This section outlines common issues and their solutions with regards to adding and removing features, reinstalling or repairing your installation, and uninstalling products.

When adding or removing features, how can I tell what features get installed by default?

To quickly see what gets installed during a Typical, default installation, click the Restore Defaults button on the Add/Remove Features page.

Is it possible to change the installation folder when adding or removing features?

Once your product is installed, you cannot change the installation path from the Add/Remove Features page. Changing the path while adding features results in program corruption, so it is not an option.

When should I reinstall the product instead of a repair?

You should reinstall your product if you accidentally delete or alter files that are required by the program. Missing or altered files adversely affect the performance of your product and cause error messages when you try to execute a command or find a file.

If an attempt to repair an installation fails, reinstalling is the next best option.

Do I need my original disc(s) to reinstall my product?

When performing a reinstall of the product, you are prompted to load your original disc(s). Installation data is cached locally on your drive and that data is reused when reinstalling.

When I uninstall my software, what files are left on my system?

If you uninstall the product, some files remain on your system such as files you created or edited (drawings or custom menus).

Your license file also stays on your workstation when you uninstall your product. If you reinstall on the same workstation, the license information remains valid and you do not have to reactivate the product.

Glossary of Installation Terms

2

The Glossary describes terms specific to the installation of Autodesk software products.

The Glossary also includes acronyms used in the installation process of Autodesk software products.

Acronyms

The following is a list of acronyms used in the installation process of Autodesk software products.

MSI

Microsoft installer that supports a variety of parameters that can be scripted.

MSP

Microsoft patch file (see patch).

Terms

The following is a list and description of terms specific to the installation process of Autodesk software products.

activate

Part of the Autodesk software registration process, it allows you to run a product in compliance with the product's end-user license agreement.

Active Directory

A directory service from Microsoft that is part of Windows 2000 and Windows 2003 Server that manages the identities and relationships that make up network environments.

directory service

A network service that identifies all resources on a network and makes them accessible to users and applications. Resources include email addresses, computers, and peripheral devices such as printers. Ideally, the directory service should make the physical network topology and protocols transparent so that a user on a network can access any resource without knowing where or how it is physically connected. Virtually all directory services are based on the X.500 ITU standard.

FLEXnet

License management technology from Acresto™ Software, Inc.. FLEXnet provides administrative tools that help to simplify management of network licenses. FLEXnet can be used to monitor network license status, reset licenses lost to a system failure, troubleshoot license servers, and update existing license files.

License Transfer utility

Allows you to use an Autodesk product on more than one computer without purchasing a separate license for each computer.

multi-seat stand-alone installation

A type of installation where multiple stand-alone seats of the program are installed using a single serial number.

network license installation

A type of installation where you install the program to workstations with the files and registry entries that allow the program to communicate with the Network License Manager.

partial profile

A profile that contains partial registry information corresponding to a subset of the options available from the Files tab of the Options dialog box.

patch

A software update to an application.

power user

A user with rights to access and write to the *Program Files* folder and the *HKEY_Local_Machine* folder of the registry.

pull technology

An installation technology that requires user interaction to complete the installation.

scripting

The process of using scripting languages such as VB Script to facilitate the deployment of software packages.

service pack

Autodesk terminology for an application patch.

silent mode

An installation that proceeds without any explicit user input. No dialog boxes are presented that require interaction from the user.

Autodesk Licensing Guide

Stand-Alone Licensing Guide

3

Stand-Alone Licensing

A stand-alone license allows you to run an Autodesk® product on a single workstation.

Introduction

Stand-alone licensing allows you to use your Autodesk product in trial mode for a given number of days from the first time you launch the product. The number of days that a trial mode is active differs between Autodesk products. You can activate your license at any time before the trial period expires.

When you activate your product, you receive an activation code. If you activate online, your activation code is automatically retrieved from Autodesk and the product starts. Activations are also available through email, fax, phone, or the Autodesk website.

The license file stays on your workstation when you uninstall your product. If you reinstall your Autodesk product on the same workstation, the license information is still valid. You do not have to reactivate the product.

Multi-Seat Stand-Alone License

A multi-seat stand-alone license allows you to install, register, and activate an Autodesk product on several workstations using a single serial number. Multi-seat licenses can be purchased through your Authorized Autodesk Reseller.

Activate Your Product

You can activate your Autodesk product either on startup or while you are running the product. If you cannot activate online, offline activation is available.

Manage your Stand-Alone License

This section provides information about advanced stand-alone licensing tasks such as license types and behaviors, viewing product information, saving your license file as a text file, updating your serial number, and transferring a license.

Check Product Information

You can view detailed information about your Autodesk product and your product license (such as the license usage type and the license behavior), and then save this information as a text file.

License usage types

NOTE All license types are available as stand-alone and network except for the Student Portfolio license, which is available as stand-alone only.

Commercial A license for a product that was purchased commercially.

Not for Resale A license for a product that is not sold commercially.

Educational (EDU)/Institution A license designed specifically for educational institutions.

Student Portfolio A license for students who are using an Autodesk product as part of their curriculum.

License behaviors

Trial A license that allows individuals to try the product in trial mode for a specified number of days. The trial period starts the first time you launch your product. When the trial period expires, the product must be registered and activated to continue use.

Permanent Allows permanent use of an Autodesk product.

Term Extendable Allows access to an Autodesk product for a limited time. The term can be extended at any time.

Term Non-Extendable Allows access to an Autodesk product for a limited time. The term cannot be extended.

View Product Information

To view product information:

- 1 Launch MotionBuilder.
- 2 Select Help > About MotionBuilder from the main menu bar.
- 3 In the About MotionBuilder 2011 window, click Product License Information.
- 4 In the Product License Information dialog box that appears, view details about your product and the product license.
- 5 In the Product License Information dialog box, click Close.

Save License Information as a Text File

You can save your product license information as a text file.

To save license information as a text file:

- 1 Launch MotionBuilder.
- 2 Select Help > About MotionBuilder from the main menu bar.
- 3 In the About MotionBuilder window, click Product License Information.
- 4 In the Product License Information dialog box, click Save As.
- 5 In the Save As dialog box, name the file, choose a location where you want to save the file, and then click Save.
- 6 In the Product License Information dialog box, click Close.

Update your Serial Number

If you installed your product with the trial serial number (000-00000000), you can update that trial serial number with a valid serial number. Your valid serial number is located on the outside of the product packaging or in the *Autodesk*

Upgrade and Licensing Information email you received if you downloaded your product.

NOTE If you have lost your serial number, contact the Autodesk Business Center (ABC) at 800-538-6401 for assistance.

When you register and activate your product, you are asked for the product serial number, which is automatically entered upon completion of the activation process.

If you have a multi-product bundle of software that uses a single serial number, only the first product you register and activate displays the updated serial number. For other products to display the serial number, you must update it from the Help menu.

To update your serial number:

- 1 Launch MotionBuilder.
- 2 Select Help > About MotionBuilder from the main menu bar.
- 3 In the About MotionBuilder dialog box that appears, click Product License Information.
- 4 In the Product License Information dialog box, click Update.
- 5 In the Update the Serial Number dialog box, enter your product serial number.

The serial number is located on the outside of the product packaging or in the *Autodesk Upgrade and Licensing Information* email you received if you downloaded your product.

NOTE If you have lost your serial number, contact the Autodesk Business Center (ABC) at 800-538-6401 for assistance.

- 6 Click OK. You can now see the updated serial number.

Transfer your Stand-Alone License

You can use an Autodesk product on more than one computer without purchasing a separate license for each computer. License transfers are only supported on products that require the creation of an Autodesk ID as part of the registration and activation process.

About the License Transfer Utility

The License Transfer Utility transfers a product license online from one computer to another, and ensures that the product works only on the computer that contains the license. The License Transfer Utility is a custom stand-alone installation option. During installation, a shortcut is created. A shortcut is installed once per product, per workstation.

You may want to transfer a license to a computer temporarily (if you want to use an Autodesk product on your laptop, for example) or permanently (if the computer where you originally activated your Autodesk product is being replaced). You can leave the license on the secondary computer indefinitely, or you can move the license between computers as needed.

License transfers rely on the product's serial number. Before an Autodesk product can be exported, it must be activated with the serial number and product key. During license import, a previously activated and exported license is imported to a product or product suite installed with the same serial number. The activation is transferred to the import computer, completing the license transfer.

NOTE The number of concurrent exports you can have, is equal to the number of seats you own. For example, if you own one seat you can have one export in progress at a time. You cannot complete another export until the one in progress has been imported. Similarly, if you have five seats, you can have up to five concurrent exports in progress at one time.

NOTE When you upgrade your Autodesk product (non-subscription), you can no longer perform online license transfers of the previous license.

NOTE Although the License Transfer Utility allows you to transfer your product license between computers, your license agreement may not allow the installation of an Autodesk product on more than one computer. Read your license agreement to find out whether your product license permits the use of the License Transfer Utility.

To transfer a license you must have an Internet connection, have an Autodesk product installed on both computers, and perform an online export and import of the license.

Install the Autodesk Product

Before you can use the License Transfer Utility to transfer licenses, you must have an Autodesk product installed on all computers involved in the transfer.

To install the Autodesk product

- 1 Install and activate the Autodesk product on a computer.
See your product's installation instructions for complete details.
- 2 Install the Autodesk product on any other computer that will be using the License Transfer Utility. You do not have to register or activate the product on this computer.
See your product's installation instructions for complete details.

Export a License

A license is exported when the License Transfer Utility moves a product license from a computer to the online Autodesk server.

The license can be exported as public or private. Exporting a license as public means that you are not reserving the license and anyone using the same serial number and their own user ID and password can import that license. Exporting a license as private means that you are reserving that license for yourself and the license can only be imported with the same serial number, your user ID, and your password.

NOTE An Internet connection is required to export a license.

To export a license:

- 1 On the computer where you want to export the license, do the following:
 - (Windows XP/Windows 7/Windows Vista) Click Start ► All Programs ► Autodesk ► *[Autodesk Product]* ► License Transfer Utility.

The License Transfer Utility displays the Autodesk product name and serial number.
- 2 In the License Transfer Utility, click Sign In.
- 3 On the Log In page, enter your Autodesk user ID and password and click Log In.
- 4 On the License Export page, confirm the export information.

- 5 If you want to make the license available as a public import, click Make the license available as a public import.
- 6 Click Export.
- 7 On the License Export Confirmation page, click Finish.

Import a License

A license is imported when the License Transfer Utility moves a previously exported product license from the online Autodesk server to a computer.

When you have exported a product license from a computer, you complete the license transfer process by importing that license onto a computer. A license is imported when the License Transfer Utility creates an active license on a computer, allowing your Autodesk product to run on this computer.

When you use the License Transfer Utility to import a license to a computer, you are not activating the product on the computer; you are simply transferring your activation to this machine.

NOTE An Internet connection is required to import a license.

To import a license:

- 1 On the computer where you want to import the license, do the following:
 - (Windows XP/Windows 7/Windows Vista) Click Start ► All Programs ► Autodesk ► *[Autodesk Product]* ► License Transfer Utility.

The License Transfer Utility displays the Autodesk product name and serial number.

- 2 In the License Transfer Utility, click Sign In.
- 3 On the Log In page, enter your Autodesk user ID and password and click Log In.
- 4 On the License Import Confirmation page, click Finish.

The license is now imported to the computer and you can run your Autodesk product on this computer. If you want to transfer the license to another computer, repeat the export and import procedures.

To import a license to replace a trial license:

- 1 On the computer where you want to import the license, do the following:
 - (Windows XP/Windows 7/Windows Vista) Click Start ► All Programs ► Autodesk ► [Autodesk Product] ► License Transfer Utility.

The License Transfer Utility displays the Update the Serial Number and Product Key options.

- 2 Enter the serial number and product key to update your Autodesk product and click Update.

The License Transfer Utility displays the updated serial number.

- 3 In the License Transfer Utility, click Sign In.

- 4 On the Log In page, enter your Autodesk user ID and password and click Log In.

- 5 On the License Import Confirmation page, click Finish.

The license is now imported to the computer and you can run your Autodesk product on this computer. If you want to transfer the license to another computer, repeat the export and import procedures.

Troubleshoot a Stand-Alone License Error

When you activate your Autodesk product, only the computer that you used to activate the product is licensed to run the product. If you make certain changes to your computer, your stand-alone license might fail. You will receive a license error and you will not be able to use your product. This section discusses ways in which you can troubleshoot a license error.

Some license errors require you to reactivate your product. If you need to reactivate your product, the Product Activation wizard is displayed when you try to run the product. To reactivate your product, follow the instructions in the Product Activation wizard.

The following topics offer more details regarding specific errors.

Hardware Changes

If you replace or reconfigure hardware on the computer where your Autodesk product license resides, the stand-alone license might fail. You will not be able to use your product.

To prevent damage to your product license, use the License Transfer Utility to export your license file. After you make the hardware change, you can import the license file back. For instructions about using the License Transfer Utility, see [Transfer Your Stand-Alone License](#).

NOTE If you get a license error when you change your hardware, you may have to reactivate your license. See [Activate Your Product](#) on page 24.

Reinstalling an Operating System

If you reinstall your operating system on the computer where your Autodesk license resides, the license might fail. You will not be able to use your product.

To resolve a license error in this case, you must reactivate your product. See [Register and Activate MotionBuilder](#) on page 9.

To prevent a license error when you reinstall an operating system:

- 1 Locate one of the following folders and make a backup copy:
 - (Windows XP) C:\Documents And Settings\All Users\Application Data\FLEXnet
 - (Windows 7/Windows Vista) C:\ProgramData\FLEXnet
- 2 Reinstall the operating system and reinstall the Autodesk product.
- 3 Paste the license folder to the same location from which you originally copied the folder in step 1.

You can now run your Autodesk product.

Changing the System Date and Time

Your product license allows for time changes to the system clock within two days of the current time. If you set your system clock back more than two days, the next time you start your product, you will receive a message that gives you the option of correcting the system clock. If you do not correct the system clock, you receive a license error.

To prevent a license error due to a change in system date and time

- Make sure that your computer's system date and time are accurate when you install and activate your Autodesk product.

Network Licensing Guide

4

Network Licensing

A network license allows you to run an Autodesk product on a network. Network licenses can be purchased through your Authorized Autodesk Reseller.

Setting up network licenses for an Autodesk product requires careful planning and execution. This section gives you instructions about how to set up a network licensed environment, and assumes that you are familiar with the terminology and processes required to set up an Autodesk product to run on a network.

Plan Your Network Licensing

This section contains information that you need to know before you set up a network license server. The section includes information about supported license server models, license operation and availability, network license file definitions and parameters, license file examples, license types and behaviors, and the license server heartbeat signal.

System Requirements for the Network License Manager (Windows)

Make sure that your network license server meets the minimum recommended requirements. See the following tables for hardware and software requirements.

NOTE The Network License Manager supports Ethernet network configurations only.

Hardware and software requirements for the network license server (Windows)

Hardware/Software	Requirement
Operating System	Windows® 7® 32-bit
	Windows 7 64-bit
	■ Windows 7 Starter (32-bit)
	■ Windows 7 Home Basic (32-bit)
	■ Windows 7 Home Premium
	■ Windows 7 Professional
	■ Windows 7 Ultimate
■ Windows 7 Enterprise	
Operating System	Windows Vista 32-bit SP2 or later
	Windows Vista 64-bit SP2 or later
	■ Windows Vista Enterprise
	■ Windows Vista Business
	■ Windows Vista Ultimate
	■ Windows Vista Home Premium and Basic (32-bit)
■ Windows Vista Home Premium (64-bit)	
Operating System	Windows XP 32-bit SP2 or later
	Windows XP 64-bit SP2 or later
	■ Windows XP Home
■ Windows XP Professional	
Operating System	Windows Server 32-bit SP1 or later
	Windows Server 64-bit SP1 or later
	■ Windows 2008 Server R2
	■ Windows 2008 Server
	■ Windows 2003 Server R2
■ Windows 2003 Server	

Hardware and software requirements for the network license server (Windows)

Hardware/Software	Requirement
Computer/processor	Intel® Pentium® III or higher 450 Mhz (minimum)
Network interface card	Compatible with existing Ethernet network infrastructure NOTE The Network License Manager supports multiple network interface cards, but at least one must be an Ethernet card.
Communication protocol	TCP/IP NOTE The Network License Manager uses TCP packet types.
Browsers	Internet Explorer® 6 Internet Explorer 7 Internet Explorer 8
FLEXnet	11.7.0.0

Virtual Machine Support (Windows)

Hardware	Virtualizer	Virtual OS
Intel PC 64	Windows 2008 or Windows 2003R2 servers running on VMware® ESX3.5 Update 3 (License Manager Only)	Vista 64-bit, Vista 32-bit, Windows XP 32-bit, Windows 7 32-bit (Home Premium, Professional, Ultimate, and Enterprise), Windows 7 64-bit, Windows Server 32-bit, Windows Server 64-bit

Plan Your License Server Configuration

You must decide which license server model to use for managing your Autodesk product licenses on a server. Autodesk supports the following network license server models:

- Single license server model
- Distributed license server model
- Redundant license server model

Single License Server Model

In the single license server model, the Network License Manager is installed on a single server, so license management and activity is restricted to this server. A single license file represents the total number of licenses available on the server.

Advantages of the Single License Server Model

- Because all license management takes place on a single server, you have just one point of administration and one point of failure.
- Of the three license server models, this configuration requires the least amount of maintenance.

Disadvantage of the Single License Server Model

- If the single license server fails, the Autodesk product cannot run until the server is back online.

Distributed License Server Model

In the distributed license server model, licenses are distributed across more than one server. A unique license file is required for each server. To create a distributed license server, you must run the Network License Manager on each server that is part of the distributed server pool.

Advantages of the Distributed License Server Model

- Servers can be distributed across a wide area network (WAN); they do not need to exist on the same subnet.
- If one server in the distributed server pool fails, the licenses on the remaining servers are still available.
- If you need to replace a server in the distributed server pool, you do not need to rebuild the entire pool.
- Server replacement is easier than in a redundant server pool, where you must reactivate the entire pool.

Disadvantage of the Distributed License Server Model

- If a server in the distributed server pool fails, the licenses on that server are unavailable.

Redundant License Server Model

In the redundant license server model, you use three servers to authenticate a single license file. One server acts as the master, while the other two provide backup if the master server fails. With this configuration, licenses continue to be monitored and issued as long as at least two servers are still functional. The license file on all three servers is the same. You must install the Network License Manager on each server.

In the redundant license server model, all servers must reside on the same subnet and have consistent network communications. (Slow, erratic, or dial-up connections are not supported.)

Advantage of the Redundant License Server Model

- If one of the three servers fails, all licenses that are managed in the server pool are still available.

Disadvantages of the Redundant License Server Model

- If more than one server fails, no licenses are available.
- All three servers must reside on the same subnet and have reliable network communications. The redundant server pool does not provide network fault tolerance.
- If one of the three servers is replaced, the complete redundant server pool must be rebuilt.
- If your Autodesk product supports license borrowing and licenses are borrowed from a redundant license server pool, you must restart the license server after you stop the Network License Manager.

Learn About Your License

In this section, you learn about license operation and availability, the license file, license types and behaviors, and the heartbeat signal.

License Operation and Availability

When you start an Autodesk product, the product determines the server from which it should try to obtain a license. The product then requests a license through the TCP/IP network protocol to the license server.

If the number of available licenses has not been exceeded on the license server, the Network License Manager assigns a license to the workstation. A product session then starts on the workstation, and the number of available licenses on the license server is reduced by one.

Likewise, when you exit a product, the Network License Manager frees a license for another user. If you run multiple sessions of an Autodesk product on an individual workstation, only one license is used. When the last session is closed, the license is freed.

The following three processes manage the distribution and availability of licenses:

- **License manager daemon** (*lmgrd.exe*). Handles the original contact with the application, and then passes the connection to the vendor daemon. The *lmgrd.exe* daemon is used to communicate with the vendor daemon only; *lmgrd.exe* does not authenticate or dispense licenses, but rather passes user requests to the vendor daemon. By using this approach, a single *lmgrd.exe* daemon can be used by multiple software vendors to provide license authentication. The *lmgrd.exe* daemon starts and restarts the vendor daemons as needed.
- **Autodesk vendor daemon** (*adskflex.exe*). Tracks the licenses that are checked out and the workstations that are using them. Each software vendor has a unique vendor daemon to manage vendor-specific licensing. As its name implies, the *adskflex.exe* vendor daemon is specific to Autodesk products.

NOTE If the *adskflex.exe* vendor daemon terminates for any reason, all users lose their licenses until *lmgrd.exe* restarts the vendor daemon or the problem causing the termination is resolved.

- **License file.** A text file that has vendor-specific license information.

You can run only one Autodesk vendor daemon (*adskflex.exe*) on your license server. This means that if you plan to serve licenses for multiple Autodesk products that were purchased individually (not as part of a suite or bundle) you must combine the license file contents for the products into one license file.

For example, if you plan to serve MotionBuilder licenses from a machine that is already serving 3ds Max licenses, you must append the contents of your MotionBuilder license file to the 3ds max license file. See Example of a License File for Combined Autodesk Product Versions.

TIP You can use the following commands to query the status of your license server and determine how many licenses you have in total, how many are in use, and to verify that your license server is up and running.

- (Windows) `lmutil lmstat -a -c <license file>` (where *<license file>* is your license file name)
-

License Files

The network license file you receive from Autodesk contains licensing information required for a network installation. You obtain license file data when you register your Autodesk product.

The license file contains information about network server nodes and vendor daemons. It also contains an encrypted digital signature that is created when Autodesk generates the file.

The license file is located in a network location that you specify in the Deployment wizard. That network location must be accessible to every user who runs the product from a network installation.

NOTE If you are already running a network license server for a separate Autodesk product, such as 3ds Max, you must append the contents of your MotionBuilder license file to the contents of the license file for the other Autodesk product. See [Example of a License File for Combined Autodesk Product Versions](#).

The following table defines each license file parameter.

Definitions of license file parameters

Line	Parameter	Definition	Example
SERVER	Host Name	Host name of the server where the Network License Manager resides	LABSERVER
	Host ID	Ethernet address of the server where the Network License Manager resides	03D054C0149B
USE_SERVER	[None]		
VENDOR	Vendor Daemon	Name of the server-side Autodesk vendor daemon	<i>adskflex.exe</i>

Definitions of license file parameters

Line	Parameter	Definition	Example
	Port Number	Network port number reserved and assigned for use only by Autodesk products running the Autodesk vendor daemon	port=2080
PACKAGE	Name	Name of feature code group	<i>SERIES_1</i>
	Version	Internal version number reference	1.000
	COMPONENTS	List of feature codes supported in the package	COMPONENTS= "526000REVIT_9_OF\ 51200ACD_2007_OF\ 513001IN- VBUN_11_OF"
	OPTIONS		OPTIONS=SUITE
	SUPERSEDE	Replacement for any existing Increment line of the same feature code from any license files on the same license server that have a date earlier than the defined Issue Date	SUPERSEDE
	SIGN	Encrypted signature used to authenticate the attributes of the license file	SIGN=0 SIGN2=0
INCREMENT	Feature Code	Product supported by the license file	51200ACD_2007_OF
	Expiration Date	Amount of time the licenses are available	permanent
	Number of Licenses	Number of licenses supported by the license file	25
	VENDOR_STRING	License usage type and license behavior of the product that is supported by the license file	COMMERCIAL

Definitions of license file parameters

Line	Parameter	Definition	Example
	BORROW	Definition of the license borrowing period for the licenses defined under the same increment line. In this example, the maximum period that licenses can be borrowed is 4320 hours (180 days), unless otherwise noted (for example, BORROW=2880 means that licenses can be borrowed for a maximum of 2880 hours, or 120 days). License borrowing is disabled when this parameter is absent in the license file.	BORROW=4320
	DUP_GROUP	Definition of multiple license requests when the same user and same host share the same license	DUP_GROUP=UH
	ISSUED	Date that the license file was generated by Autodesk	15-jul-2006
	Serial Number	Serial number of the Autodesk product	123-12345678
	SIGN	Encrypted signature used to authenticate the attributes of the license file	SIGN=6E88EFA8D44C

License File Examples

License file examples are provided in this document to help you understand how the license files work for your particular network setup. Autodesk provides a standard license file for individual products and a license file with additional parameters for products that are sold both individually and as part of a product set.

- **Standard License File.** If you purchase one or more individual products that are not offered as part of a suite of products, you receive a standard license file.

- **Standard License File with Additional Parameters.** If you purchase Autodesk products that are included in a product set and are also sold as an individual product, you receive a standard license file with additional parameters included in the license file. The additional parameters define the sequence for license usage so that the individual product license is used before the license for the product set.

Autodesk license file examples include a license file not specific to a product, completed license files for single, distributed, and redundant server models, a combined product version license file, and an example of additional parameters added to a standard license file.

Example of a License File Not Specific to a Product

Here is an example of the contents of a license file and the parameters associated with each line:

```
SERVER ServerName HostID
USE_SERVER
VENDOR adskflex port=portnumber
INCREMENT feature_code Adskflex Version ExpDate NumberofLicenses
\
VENDOR_STRING=UsageType:Behavior BORROW=4320 SUPERSEDE \
DUP_GROUP=DupGrp ISSUED=IssueDate SN=SerialNumber SIGN= \
```

Example of a License File for a Single or Distributed Server

Here is an example of a completed license file for a single or distributed license server model:

```
SERVER XXHP0528 0019bbd68993
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 57600ACD_2009_0F adskflex 1.000 permanent 5 \
VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1393 \
E368 816E D417 C1CD 7DBD 7B90 1354 D6F0 48FE EBB8 9C84 C3AF \
7D79 BEE1 0181 0655 76FF 996C B707 14B5 D4DE A3FE 0B2D 2D36 \
057C A579 7866 26BF 44E2" SIGN2="1280 943B 53A7 9B93 E00B D967
\
D821 BD37 BE6D B78A F074 B223 88AA 242C DD0A 1292 D56F 4108 \
62CD FA35 E365 0736 A011 7833 8B35 7BFF DAD8 34A8 452F 2EB4"
```

Example of a License File for a Redundant Server

Here is an example of a completed license file for a redundant license server model:

```
SERVER CCN12378042 001cc4874b03 27005
SERVER XXHP0528 0019bbd68993 27005
SERVER CCN12378043 001cc4874b10 27005
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 57600ACD_2009_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=10-Jan-2008 SN=123-12345678 SIGN="11C4 \
  CA79 07FC 7AD0 409A 6E04 6E98 D76C 197C 0416 076C B211 1CDD \
  D0AB 698B 16BF 7A0E D4F8 1CFE 2985 644F 64CD CECE 0DDB 5951 \
  3262 7C31 13A8 F08F 55B2" SIGN2="19A6 FDA3 2ED5 5301 8675 7B81
  \
  1B0E 451B 19F1 1A99 C8E9 CBA6 8CB3 6AC3 8B38 1519 13F2 2373 \
  82AE 55E5 1A25 4952 4458 F3A2 6F28 D25D 1DC0 E066 209B 0953"
```

NOTE The redundant server model requires the addition of a port number (the default is 27005) for each server.

Example of a License File for Combined Autodesk Product Versions

You can combine a license file for different releases of the same Autodesk product or for different Autodesk products, and run all products from one license server. For example, you can combine a license file for AutoCAD 2009 with license files for Autodesk Maya® 2009 and AutoCAD Map.

If your license server distributes licenses for multiple Autodesk products that were purchased individually (not part of a suite or bundle), you must combine the network license information from all products into one license file.

Here is an example of the contents of a combined license file for AutoCAD 2008 and AutoCAD 2009:

```
SERVER XXHP0528 0019bbd68993
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 57600ACD_2009_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1393 \
  E368 816E D417 C1CD 7DBD 7B90 1354 D6F0 48FE EBB8 9C84 C3AF \
  7D79 BEE1 0181 0655 76FF 996C B707 14B5 D4DE A3FE 0B2D 2D36 \
  057C A579 7866 26BF 44E2" SIGN2="1280 943B 53A7 9B93 E00B D967 \
  D821 BD37 BE6D B78A F074 B223 88AA 242C DD0A 1292 D56F 4108 \
  62CD FA35 E365 0736 A011 7833 8B35 7BFF DAD8 34A8 452F 2EB4"
INCREMENT 54600ACD_2008_0F adskflex 1.000 permanent 3 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1E6E \
  4B61 5712 4766 92A0 6782 9EF4 3F47 56A1 1F38 6DE8 C0C7 90AC \
  7289 152E 0EA2 CC0D 3F10 577A 0489 CEB6 10D5 FBCC B552 0C9D \
  5966 91A6 59F0 2788 FACE" SIGN2="1DDF 3B9D 3392 71D5 AB08 7E05 \
  8497 111E 092F 0E54 8DC2 2BED 17C2 2CC1 981B 0EC2 BC15 8F00 \
  C79A ABFD 2136 BABA 2EDF E941 EA53 32C6 597F F805 5A8A 599A"
```

Example of Additional Parameters in a License File

For Autodesk products that are included in a product set and are also sold as an individual product, licenses are allocated based on a sequence of priorities defined in the license file. For those products, information similar to the following example appears in a license file:

```
SERVER Server1 1a34567c90d2
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 54600ACD_2008_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2007 SN=123-12345678 SIGN="0247 \
  45D6 87C4 27A5 7F9E F24A ED3D 61E4 6B3B CC5C AD77 B865 9EA8 \
  3D62 0792 0F67 19E7 57E7 FAFA A48B D582 335A EC16 1FE5 B70D \
  76AB 6488 61CC DE5E F5B7" SIGN2="09FD 0850 7CF1 F447 9F05 9FA3 \
  2A0A 38D6 83FC 1746 F3F5 5A72 6250 E002 DE0B 0E6E F88C AC95 \
  136F 87F2 A945 E4C4 A97F 44B5 74EE 83F3 3F3E 1579 B981 8994"
```

Package License File Examples

Autodesk offers a package license file option, which allows you use of a set of products that are packaged and sold together. The package license file contains a set number of licenses for four different versions of your software. Running an instance of any one of the versions uses one license in the package. Packaged license files support prior versioning for subscription users. Package license files operate under the following guidelines:

- Package license files come with the current version of the software and three previous versions of the same product.
- License files may be combined with license files for different products. For more information about combining license files, see [Example of a Package License File for Combined Autodesk Product Versions](#) on page 48.
- Package license files cannot be combined with non-package license files for product versions contained in the package. For example, you cannot combine a *Autodesk Product 2009* package license file with a regular license file for *Autodesk Product 2008*, *2007*, or *2006*.
- Both the PACKAGE and INCREMENT sections of the license are required for licensing to work properly. When you combine license files, be sure to include both of these sections.
- License borrowing, option files, and licensing cascading work the same for package licenses as they do for regular license files.
- A new license file will supersede an older license file.

The following sections provide package license file examples for single, distributed, and redundant license servers, and combined Autodesk product versions.

Example of a Package License File for a Single or Distributed Server

Here is an example of a completed license file for a single or distributed license server model:

```
SERVER Server1 1a34567c90d2
USE_SERVER
VENDOR adskflex port=2080
PACKAGE SERIES_1 adskflex 1.000 COMPONENTS="54700REVIT_2009_0F \
54600ACD_2009_0F 51300INVBUN_11_0F" OPTIONS=SUITE SUPERSEDE \
ISSUED=09-Jan-2008 SIGN="1707 9EAC CBCB 2405 692E 4A89 \
AA26 30CC 2AC2 D6B3 A61B AB5E 492E 3EBD 0B48 4E75 193A DA82" \
FC45 C009 E360 944A 14BA E99C 9B24 5A1B 4A44 083A BE5F 3827 \
SIGN2="004A FC90 AB47 3F6B 59BC 0E6D 6681 6971 A76A BA52 98E2
\
5671 26B3 0E78 791B 109F 0591 7DC3 F09F 4D8D 4FB7 E341 4A03 \
CD68 1D77 27F8 8555 9CF7 DEDD 9380"
INCREMENT SERIES_1 adskflex 1.000 permanent 100 \
VENDOR_STRING=commercial:permanent BORROW=4320 DUP_GROUP=UH \
SUITE_DUP_GROUP=UHV SN=123-12345678 SIGN="1707 9EAC CBCB \
692E 4A89 FC45 C009 E360 944A 14BA E99C 9B24 5A1B 4A44 BE5F \
3827 AA26 30CC 2AC2 D6B3 A61B AB5E 492E 3EBD 0B48 DA82" \
SIGN2="004A FC90 AB47 3F6B 59BC 0E6D 6681 6971 A76A BA52 \
5671 26B3 0E78 791B 109F 0591 7DC3 F09F 4D8D 4FB7 E341 4A03 \
CD68 1D77 27F8 8555 9CF7 DEDD 9380"
```

Example of a Package License File for a Redundant Server

Here is an example of a completed license file for a redundant license server model:

```
SERVER 1a34567c90d2 27005
SERVER 2a34567c90d2 27005
SERVER 3a34567c90d2 27005
USE_SERVER
VENDOR adskflex port=2080
PACKAGE 64300ACD_F adskflex 1.000 COMPONENTS="57600ACD_2009_0F \
54600ACD_2008_0F 51200ACD_2007_0F 48800ACD_2006_0F" \
OPTIONS=SUITE SUPERSEDE ISSUED=27-May-2008 SIGN="1092 05D8 \
A206 276B 2C84 EFAD ACA5 C54B 68A4 653E C61F 31DE C8CE B532 \
CFBB 0006 5388 347B FDD6 A3F4 B361 7FD4 CDE4 4AAC 0D11 B0EF \
4B44 BFD6 3426 97DD" SIGN2="0670 B01A D060 0069 FF25 F1CD D06B
\
314E E7C9 3552 5FFA 4AC7 28A7 C897 F56A 19BB FB1C 754E 6704 \
DEEA AC4E F859 2E9B 64B6 ODD0 9CCE 9556 269F EAC0 2326"
INCREMENT 64300ACD_F adskflex 1.000 permanent 50 \
VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
DUP_GROUP=UH SUITE_DUP_GROUP=UHV ISSUED=27-May-2008 \
SN=399-99999999 SIGN="1B5B 8D70 4CAD 32E5 9CA2 82E0 5C47 291C
\
35AB 9B9C 5B3E 5067 F61B 4139 1B32 0716 1FD3 5105 A991 B78E \
9D1E 63AB BC23 0D1E B70C 2A05 E1C1 F605 ABB1 2EA8" SIGN2="01D6
\
31F5 2951 4500 E5C8 058F 7490 9789 9EF4 CBED DA27 5F06 6780 \
9033 2018 0C3B E1E0 3580 E60E C2BB B4AB 8D6A 4245 3059 8CA6 \
2EFE DFAE 027F 2ABE 3F2B"
```

Example of a Package License File for Combined Autodesk Product Versions

Here is an example of a completed license file for combined Autodesk product versions:

```

SERVER servername 123456789111
USE_SERVER
VENDOR adskflex port=2080
PACKAGE 64300ACD_F adskflex 1.000 COMPONENTS="57600ACD_2009_OF \
54600ACD_2008_OF 51200ACD_2007_OF 48800ACD_2006_OF" \
OPTIONS=SUITE SUPERSEDE ISSUED=25-Jun-2008 SIGN="03EF DE18 \
8046 0124 4EA4 6953 F82D 3169 7C24 D0DE E58E 8168 FFA3 D891 \
B43B 08D8 7E7F C6ED CBCC FE2A BB0A 4566 C2AE F1C1 D373 8348 \
E6E3 884A E398 1C78" SIGN2="07AC D696 8844 D19F AB00 8B75 53A3
\
2F76 91DF AED0 3231 1506 0E6B ADC6 C3B8 1797 93B5 9756 8C0F \
8811 56E6 B2BA 0523 FE2E 82B7 1628 076F 173B F37C 7240"
INCREMENT 64300ACD_F adskflex 1.000 permanent 2 \
VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
DUP_GROUP=UH SUITE_DUP_GROUP=UHV ISSUED=25-Jun-2008 \
SN=399-99999999 SIGN="1CCB E88D B819 8604 06FA 9AEE 42F1 CBEA
\
37B9 3CFA A0A8 697F 9CB1 8354 6256 05ED 69D4 D2FF D512 6A2E \
D5DD B722 EF5B 3172 BA95 4625 F8D3 DD24 BB39 6A58" SIGN2="0DFE
\
FA6F C378 20E0 2622 BE52 B434 F99F 2681 2B93 64F2 CE0C 7F4A \
7024 B3D1 051A 6920 72BD DE35 8920 E6A1 C8D6 AF23 7BE7 CC91 \
6916 70B1 9E80 AB07 1644"
PACKAGE 64800INVPRO_F adskflex 1.000 \
COMPONENTS="59600INVPRO_2009_OF \
55300INVPRO_2008_OF 51400INVPRO_11_OF 49000INVPRO_10_OF" \
OPTIONS=SUITE SUPERSEDE ISSUED=25-Jun-2008 SIGN="1306 5990 \
F8A1 56FB 1D8A 9DA7 D6AE 8E9E F6EC 2862 367A 36E2 C5FB E6E1 \
4AAA 0128 8C2D 95FD 09B2 ABA1 6F98 A0A3 70DE 3220 6835 7E51 \
3849 9D81 8BDC 9DC1" SIGN2="0021 AA08 F2E7 8AEB 5345 341A 7E42
\
3001 B8C5 DFC2 6EB8 87C5 C04A AE43 A10F 1DA1 EF8A F0FA 10F5 \
AC81 1E22 789F A18D 650F 6BBB 563A BDA5 DD1C 82EC 27F6"
INCREMENT 64800INVPRO_F adskflex 1.000 permanent 2 \
VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
DUP_GROUP=UH SUITE_DUP_GROUP=UHV ISSUED=25-Jun-2008 \
SN=399-99999966 SIGN="0BE4 51F4 570C DC48 5E66 F952 629E EDF0
\
019C 6FF7 0509 1FF0 D4FB 3B16 1981 073F 31EC A241 8CB3 8782 \
E655 00C6 E097 D5EF B0D8 67D3 199D 699D 2E09 B16F" SIGN2="1254
\
3E37 0CE4 F42D B7CD 858C 92FC A963 5274 770F 9354 FE29 E117 \
205D C632 0C4E AEC0 7501 9D9E FFEB D84D F154 16A1 E120 339A \

```

License Types and Behaviors

Autodesk supports dynamic product usage and license behaviors. This means that you can purchase a specific type of behavior with a specific license and change that license at a later date without having to uninstall and reinstall the Autodesk product.

NOTE All license types are available as stand-alone and network except for the Student Portfolio license, which is available as stand-alone only.

License types include the following:

- **Commercial.** A license for a product that was purchased commercially.
- **Not for Resale.** A license for a product that is not sold commercially. Not for Resale products are for evaluation or demonstration purposes only and may not be used for commercial or production use.
- **Educational (EDU)/Institution.** A license designed specifically for educational institutions.
- **Student Portfolio.** A license for students who are using an Autodesk product as part of their curriculum.

License behaviors are as follows:

- **Permanent.** Enables permanent use of an Autodesk product.
- **Term Extendable.** Enables access to an Autodesk product for a limited time. The term can be extended at any time.
- **Term Non-Extendable.** Enables an Autodesk product for a limited time. The term cannot be extended.

Heartbeat Signal

When an Autodesk product is running, it communicates with the license server at regular intervals using a communication method known as the “heartbeat” signal. If the heartbeat signal is lost, the server tries to reconnect. If the server cannot reconnect, the user receives a license error.

If the product stops working because it has lost a connection to the server, you must shut down the product, and then restart it. If the problem causing the original loss of the heartbeat signal is resolved and there are available licenses on the server, the program can be restarted.

Network License Manager

The Network License Manager is used to configure and manage the license servers. When creating a deployment, the Installation wizard prompts you for information about the license manager, such as license server model and server name.

For more information about deploying an Autodesk product from a network location, see your product's installation documentation.

Install the Network License Manager

The Network License Manager is used to configure and manage license servers. It includes the `lmgrd`, `adskflex`, and `lmutil` tools that you need to set up your license server.

You can install the Network License Manager before or after you use the Installation wizard. The order in which you install the network applications does not matter, as long as you install everything you need and you provide consistent license server information across the network applications.

If an earlier version of the Network License Manager is already installed on the computer, you should upgrade by installing the Autodesk Network License Manager into the folder where the older version was located.

To install your Network License Manager:

- 1 In the Autodesk Installation wizard, click Install Tools and Utilities.
- 2 On the Select the Products to Install page, select Autodesk Network License Manager and click Next.
- 3 Review the Autodesk software license agreement for your country or region. You must accept this agreement to proceed with the installation. Choose your country or region, click I Accept, and then click Next.

NOTE If you do not agree to the terms of the license and want to terminate the installation, click Cancel.

- 4 On the Begin Installation page, review your product selection and the current settings. If you do not want to change anything, click Install. If you want to change the install type or installation path, click Configure.
- 5 On the Select the Installation Location page, accept the default installation path (*C:\Program Files\Autodesk Network License Manager*) or Browse to specify a different path. If you enter a path that does not exist, a new folder is created using the name and location you provide. Click Next.

WARNING Do not install the Network License Manager on a remote drive. When you install the Network License Manager files, you must provide a path to a local drive. You must specify the drive letter; the universal naming convention (UNC) is not permitted.

- 6 On the Configuration Complete page, click Configuration Complete to return to the confirmation page.
- 7 On the Begin Installation page, click Install.
- 8 When the Installation Complete page displays, click Finish.

Patch the License Manager on an IPv6 Network

If you are using a license server on an IPv6 (Internet Protocol version 6) network, you must install a patch to the Autodesk Network License Manager, otherwise the license server will not work.

To install the patch:

- 1 Shut down your license server.
- 2 Back up the contents of the license manager files. By default, these are in *C:\Program Files\Autodesk Network License Manager*.
- 3 Download the patch from <http://www.autodesk.com/nlm2011-ipv6-windows>.
- 4 Unzip the patch and paste the new files over the old ones; these are located by default in *C:\Program Files\Autodesk Network License Manager*. (Four files will be overwritten.)
- 5 Restart your license server.

Obtain a License Through autodesk.com

You can register and activate your network license by going to <https://registeronce.autodesk.com> and following the on-screen instructions.

Obtain the Server Host Name and Host ID Manually

Autodesk uses the server host name, host ID, and product serial number to generate a license file.

To obtain the information manually, you can use the command prompt or you can run the *lmtools.exe* utility. If you use *lmtools.exe*, do not run it on a remote workstation.

To obtain the host name and ID using the Windows command prompt:

- 1 Do one of the following:
 - (Windows XP) Click Start > Programs > Accessories > Command Prompt.
 - (Windows Vista) Click Start > All Programs > Accessories > Command Prompt.
- 2 In the Windows command prompt, enter the following command, then press Enter:

```
ipconfig /all
```
- 3 Locate the Host Name line, and write down the host name.
- 4 Locate the Physical Address line. Write down the physical address without the dashes. This is your twelve-character host ID.

NOTE If your server has more than one network adapter, select the one that corresponds to a physical network adapter. To determine which adapters are physical: in the Windows command prompt, enter **ipconfig /all**, and then view the Description field above each physical address. If there is more than one physical network adapter, it does not matter which one you use. Devices such as VPN adapters, PPP adapters, and modems are not valid.

- 5 Close the Windows command prompt.

To obtain the host name and ID using *lmtools.exe*:

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 2 In the LMTOOLS program, click the Systems Settings tab.
- 3 On the Systems Settings tab, locate the Computer/Hostname box. Copy the host name and paste the information into a text editor.
- 4 Locate the Ethernet Address box. The Ethernet address is the host ID. It consists of twelve characters. Write down the information. If your Ethernet address is more than twelve characters, write down the first twelve characters only.

NOTE If your server has more than one Ethernet adapter, select one that corresponds to a physical network adapter.

- 5 Close *lmtools.exe*.

Configure a License Server

You configure a license server so that you can manage your Autodesk product licenses. Configure the license server with the *lmtools.exe* utility.

You should be logged in with Administrator rights when working with the LMTOOLS utility.

To configure your license server:

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 2 In the LMTOOLS program, on the Service/License File tab, make sure the Configure Using Services option is active.
- 3 Click the Config Services tab.
- 4 In the Service Name list, select the service name you want to use to manage licenses.

By default, the service name is *Flexlm Service 1*. If FLEXnet[®] is managing other software on your computer in addition to Autodesk, you can change the service name to avoid confusion. For example, you can rename *Flexlm Service 1* to *Autodesk Server1*.

NOTE If you have more than one software vendor using FLEXnet for license management, the Service Name list contains more than one option. Make sure that only one Autodesk service is listed.

- 5 In the Path to Lmgrd.exe File field, enter the path to the Network License Manager daemon (*lmgrd.exe*), or click Browse to locate the file.
By default, this daemon is installed in the *C:\Program Files\Autodesk Network License Manager* folder.
 - 6 In the Path to the License File box, enter the path to your license file, or click Browse to locate the file.
This is the path to the license file obtained through *autodesk.com* or the location where you placed the license file if you obtained it offline.
 - 7 In the Path to the Debug Log File box, enter a path to create a debug log, or click Browse to locate an existing log file.
It is recommended that you save to the *C:\Program Files\Autodesk Network License Manager* folder. The log file must have a *.log* file extension. For new log files, you must enter the *.log* extension manually.
 - 8 To run *lmgrd.exe* as a service, select Use Services.
 - 9 To start *lmgrd.exe* automatically when the system starts, select Start Server at Power Up.
 - 10 Click Save Service to save the new configuration under the service name you selected in step 4. Click Yes when prompted if you would like to save the settings to the service.
 - 11 Click the Start/Stop/Reread tab and do one of the following:
 - If a service has not yet been defined for Autodesk, click Start Server to start the license server.
 - If a service for Autodesk is already defined and running, click ReRead License File to refresh the Network License Manager with any changes made to the license file or Options file.
- The license server starts running and is ready to respond to client requests.
- 12 Close *lmtools.exe*.

NOTE Before performing any system maintenance on your license server, see Stop and Restart the License Server.

Uninstall the Network License Manager

You can uninstall the Network License Manager from the license server. When you uninstall the Network License Manager, licenses are no longer available to your users.

NOTE You must manually delete files that you created for use with the Network License Manager (such as log files, license files, and the Options file). They are not automatically deleted when you uninstall.

To uninstall the Network License Manager:

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 2 In the LMTOOLS program, click the Start/Stop/Reread tab.
- 3 On the Start/Stop/Reread tab, click Stop Server.
- 4 Close *lmttools.exe*.
- 5 In the Windows Control Panel, do one of the following:
 - (Windows XP) Double-click Add/Remove Programs.
 - (Windows 7/Windows Vista) Double-click Programs and Features.Do one of the following:
 - (Windows XP) In the Add/Remove Programs window, click Autodesk Network License Manager. Click Remove.
 - (Windows 7/Windows Vista) In the Programs and Features window, click Autodesk Network License Manager. Click Remove.
- 6 If prompted, restart your computer.

Network Licensing Tools

Autodesk Network licensing tools include FLEXnet configuration tools, license borrowing, and SAMreport-Lite. Each tool is described in the sections that follow.

NOTE MotionBuilder does not support SAMreport-Lite.

This section also includes information for updating FLEXnet and installing and configuring the Autodesk Network License Manager on a network.

FLEXnet Configuration Tools

The Network License Manager uses FLEXnet® license management technology from Acrecco Software. FLEXnet provides administrative tools that help to simplify management of network licenses. You can use FLEXnet tools to monitor network license status, reset licenses lost to a system failure, troubleshoot license servers, and update existing license files on the fly.

For information about using FLEXnet configuration tools, you can find the LicenseAdministration.pdf document in the following directory: *C:\Program Files\Autodesk Network License Manager\Docs\FlexUser\LicenseAdministration.pdf*.

Utilities for License Server Management

FLEXnet provides two utilities for managing the license server. These tools are located in the *C:\Program Files\Autodesk Network License Manager* folder.

lmtools.exe Provides a Microsoft® Windows graphical user interface for managing the license server.

lmutil.exe Provides a set of command line options for managing the license server.

You can use *lmtools.exe* or *lmutil.exe* to perform the following server management tasks:

- Start, stop, and restart the server.
- Configure, update, and reread the license file.
- Diagnose system or license problems.
- View server status, including active license status.

Stop and Restart the License Server

Before you can perform any system maintenance on your license server, you must stop the license server. When you have completed maintenance, you can restart the license server.

To stop the license server (Windows)

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 2 In the LMTOOLS program, on the Service/License File tab, select the Configure Using Services option.
- 3 Select the service name for the license server you want to stop manually.
- 4 Click the Start/Stop/Reread tab.
- 5 On the Start/Stop/Reread tab, click Stop Server.
- 6 Close *lmtools.exe*.

To restart the license server (Windows)

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 2 In the LMTOOLS program, on the Service/License File tab, select the Configure Using Services option.
- 3 Select the service name for the license server you want to start manually.
- 4 Click the Start/Stop/Reread tab.
- 5 On the Start/Stop/Reread tab, click Start Server to restart the license server.

Update FLEXnet from a Previous Version

This release of Autodesk products and later require FLEXnet version 11.7.0.0 or later. If you are currently using a version of FLEXnet that is earlier than 11.7.0.0, you need to upgrade to version 11.7.0.0 or later.

NOTE If the server where you plan to install the Autodesk Network License Manager has FLEXnet installed for another product, make sure that the version of *lmgrd.exe* is the most current version.

To determine what version of FLEXnet is installed, you need to verify the version of the following files:

Windows

- *lmgrd.exe*
- *lmtools.exe*
- *lmutil.exe*
- *adskflex.exe*

To verify the version of *lmutil.exe*, *lmtools.exe*, or *adskflex.exe* (Windows)

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.

- 2 In *lmtools.exe*, click the Utilities tab.

- 3 On the Utilities tab, enter the location of the file, or click the Browse button to locate the file and click Open. The file location should look something like this:

C:\Program Files\Autodesk Network License Manager\lmutil.exe

- 4 On the Utilities tab, click Find Version.

The version number of the file you selected is displayed. If necessary, use the following procedure to update your version of FLEXnet.

To update FLEXnet (Windows)

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Back up your license files.
- 2 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 3 In the LMTOOLS program, click the Start/Stop/Reread tab.
- 4 On the Start/Stop/Reread tab, click Stop Server.
- 5 Close *lmtools.exe*.

- 6 Note the location where the Network License Manager is installed and then uninstall the Network License Manager. For details about uninstalling the Network License Manager, see Uninstall the Network License Manager.
- 7 Install the Network License Manager. For details about installing the Network License Manager to the same location as the previous version, see Install the Network License Manager.
- 8 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Autodesk ► Network License Manager ► LMTOOLS.
 - (Windows Vista) Double-click the LMTOOLS icon on the desktop.
- 9 In the LMTOOLS program, click the Start/Stop/Reread tab.
- 10 On the Start/Stop/Reread tab, click Start Server.
- 11 Close *lmtools.exe*.

Set Up and Use an Options File

With an Options file, you set configuration options for managing licenses on each license server that you set up. An Options file sets parameters that the license file reads and the *lmgrd* program executes.

If you want to have the same license behavior on some or all of your license servers, you must save the same Options file to each of those license servers. If you want to specify different license behavior on different license servers, you must create an Options file for each license behavior. You must save each Options file to the server where you want specific license behavior.

Use the Options file to set parameters for the following server-related features:

Report log file A compressed, encrypted file is created that generates accurate usage reports on license activity for use by SAMreport-Lite. See Create a Report Log.

License borrowing If your Autodesk product supports the license borrowing feature, you can allow users to borrow an Autodesk product license from a network license server so that they can use the product without being connected to the license server. A license can be borrowed for a limited time. See Configure License Borrowing with the Options File.

License Borrowing

If you are running a network-licensed version of the program, you can borrow a license from a license server to use the program for a specified time when your computer is not connected to the network.

NOTE If you have a stand-alone version of the program, you cannot borrow a license. To check your license type, click Help menu ► About ► Product Information. In the Product Information dialog box, view your product license type.

Overview

If you are using a network-licensed version of your Autodesk product and your network administrator supports the license borrowing feature, you can borrow a product license from your network license server to use the program when your computer is not connected to the network. Your license is automatically returned to the license server at the end of the day on the return date you set when you borrowed the license. You can also return a license early.

NOTE There is a limit to the number of licenses available for borrowing. If you try to borrow a license and are notified that no licenses are available, all network licenses may already be borrowed by other users. If you are unable to borrow a license, see your network administrator for help.

Borrow a License

You can run the program when your computer is not connected to the network until your license-borrowing period ends. If you don't remember the date that a license expires, you can check the date by placing your cursor over the Borrowing icon in the program's status tray or by clicking Help ► About and using the Product Information dialog box.

When the license-borrowing period expires, the borrowed license is automatically returned to the license server. Once your computer is reconnected to the network, you can run the program from the network or borrow a license again.

Contact your network administrator to find out how you can borrow a license.

See also:

- Set Up and Use an Options File

Interaction with Other License-Borrowing Tools

Using the license borrowing feature in the program is the recommended way to borrow a license; however, some third-party borrowing tools may also be available to you. These tools are not supported or compatible with the license borrowing feature in the program. Other third-party or legacy license-borrowing tools that may be available to you are the Autodesk License Borrowing utility (shipped with Autodesk products) and the borrowing feature in *lmtools.exe*, a component of the Autodesk Network License Manager.

If another license-borrowing tool is active when you attempt to use the license borrowing feature, you should proceed as follows to borrow a license for the program:

- If you run the Autodesk License Borrowing utility that shipped with your Autodesk product and then turn on the borrowing flag for the Adskflex option or the All option, a license can be borrowed when you start the program. However, you cannot return a license until you exit and then restart the program.
- If borrowing is set in *lmtools.exe* for *all* products, you can either (a) use the other tool to borrow licenses for the program or (b) stop the borrowing process in *lmtools.exe* and then use the license borrowing feature in the program.
- If borrowing is set in *lmtools.exe* for non-Autodesk products only, you must stop the borrowing process in *lmtools.exe*. You can then use the license borrowing feature to borrow licenses for your Autodesk product. If you do not stop the borrowing process in *lmtools.exe*, the license borrowing feature will not function.

Borrow a License Window

Using the license borrowing feature, you can borrow a license from your network license server, and then use the license when your computer is disconnected from the license server; for example, when you are traveling for work.

The Borrow a License window has the following options:

Calendar Sets the date when you plan to return a borrowed license. The return date must be within the range specified by your network administrator.

Borrow a License Borrows the license from the network license server based on the return date that you specified.

Cancel Cancels the borrowing action; no license is borrowed.

Return a License

Your network license is automatically returned to the network license server on the day that the license expires. You can also return a license earlier than the date you originally selected, as long as your computer is connected to the network license server when you attempt to return the borrowed license.

Once a borrowed license is returned, you can borrow a license again as long as your computer is connected to the network license server and a license is available on the server.

Contact your network administrator to find out how you can return a license.

Network Licensing FAQs

This section outlines some common questions and their solutions with regards to software licenses and licensing your product(s).

What is the difference between a stand-alone license and a network license?

Stand-alone licensed products are registered and activated to an individual workstation. While the software can be installed on multiple systems in your facility, the license only allows one system to be operational. If you need to run more systems, you need to purchase more stand-alone licensed products, or consider converting to multi-seat stand-alone licenses.

You cannot purchase a network licensed version of an Autodesk product. However, a multi-seat stand-alone licensed version is available that does not rely upon servers to maintain licenses. Multi-seat stand-alone licensing means that each installation of your product uses a single serial number for registration and activation.

What is the benefit of using a network licensed version of the software?

Network licensed products are recommended for large production facilities, classrooms, and lab environments. The main advantage is that you can install products on more systems than the number of licenses you have purchased (for example, purchasing 25 licenses but installing on 40 workstations). At any one time, products will run on the maximum number of systems for which you have licenses. This means you get a true floating license. If software needs to be run on more systems, additional licenses can be purchased.

Since a network license option is not available for Autodesk products, a multi-seat stand-alone license is recommended for production facilities, classrooms, and lab environments. Unlike a network licensed product, you can install multi-seat stand-alone products on the maximum number of systems that the license allows. For example, you purchase a multi-seat stand-alone license for 25 seats and have 30 systems at your facility that can communicate over the Internet. Even though you can install software on all 30 systems, only the first 25 systems you start will have their licenses activated. Because the licenses are tied to each specific system, the remaining five systems will never be able to run the software unless you purchase an additional five licenses.

As long as all the systems have Internet access, products are automatically activated the first time they are launched.

How do I change the license server information I entered during the installation?

To change the license server information you entered:

- 1 Depending on your OS and on whether you installed the 32-bit or 64-bit version of MotionBuilder, navigate to either the *C:\Program Files\Autodesk\Autodesk MotionBuilder 2011 64-bit* directory or the *C:\Program Files (86)\Autodesk\Autodesk MotionBuilder 2011 32-bit* directory, to locate and open the *LICPATH.LIC* file.
- 2 Edit the line `SERVER <servername>` where *<servername>* is your license server name.

If you do not find the `LICPATH.LIC` file in this location, you can create a license file by saving a text file with the extension `.lic`, and including the following lines:

```
SERVER <servername> 0  
USE_SERVER
```

What is Internet Explorer used for?

After installing your product, you can operate in trial mode for a given number of days. Whenever you launch the program, you are prompted to activate the software. When you choose to activate the software, Internet Explorer makes this process much faster. Once you entered your registration data and submit it to Autodesk, an activation code is returned and you are not prompted again during startup.

Where can I find more information on troubleshooting network licensing?

If you experience difficulty with installation or licensing, visit <http://autodesk.com/servicesandsupport> for additional FAQ information, as well as an in-depth Knowledge Base that you can search for solutions to common installation and licensing issues and error messages.

Glossary of Licensing Terms

5

The Glossary describes terms specific to the licensing of Autodesk software products.

The Glossary also includes acronyms used in the licensing process of Autodesk software products.

Acronyms

The following is a list of acronyms used in the licensing process of Autodesk software products.

IPv6

Internet Protocol version 6

JRE (Java Runtime Environment)

A program that is required to run Java programs. This program must be installed with SAMreport-Lite.

Terms

The following is a list and description of terms specific to the licensing process of Autodesk software products.

ADSKFLEX_LICENSE_FILE

In a distributed license server configuration, the environment variable used to point a workstation to the distributed license servers.

adskflex.exe

The Autodesk vendor daemon used with the FLEXnet license technology. This daemon keeps track of the Autodesk licenses that are checked out and the workstations that are using the licenses.

borrowed license

A license that allows you to use an Autodesk product for a limited period of time without having to buy a separate license or have network access to the license server.

daemon

A program that runs continuously in the background of a computer. The daemon handles requests from the computer and then forwards the requests to other programs or processes. The Network License Manager uses two daemons: the vendor daemon (*adskflex.exe*) and the license manager daemon (*lmgrd.exe*).

debug log file

A file used with FLEXnet to log connection activity (such as license failure or starting and stopping) between the Network License Manager and the workstation.

distributed server

A license server configuration option in which several servers are used to manage license distribution. Each distributed license server has a unique license file and a fixed number of licenses. If one distributed license server fails, the other servers are still able to distribute their licenses.

Ethernet address

See [host ID](#) on page 69.

feature code

A license file parameter that represents the product that is supported by that license file.

FLEXnet

The Acrecco Software license management technology implemented in the Autodesk family of products.

heartbeat signal

The communication signal between the Network License Manager and the workstation to verify that the workstation is accessible and has an active Autodesk product session running.

host ID

The unique hardware address of a network adapter. Also known as *Ethernet address* or *physical address*.

host name

The TCP/IP name associated with a computer. FLEXnet technology uses the host name as a parameter; the host name must be distinguished from the NetBIOS (server) name.

idle

A state of inactivity in your product that prompts a network license server to reclaim a license. Inactivity is due to no mouse or keyboard activity and no commands, LISP expressions, menu macros, or scripts in progress for the period of time that is defined in the Options file. See also *license timeout*.

license file

A file used with FLEXnet that controls the number of available seats. This file must be in ASCII plain text format.

license server

A server that contains the Network License Manager.

license timeout

A feature that allows you to set up a timeout period on your license server to automatically return an idle license to the server so that it is available for use again.

licpath.lic

In both single and redundant server configurations, the file used to point the workstation to the FLEXnet license server. *Licpath.lic* is located in the root installation folder.

lmgrd.exe

The license manager daemon. This daemon handles the original contact with the program, and then passes the connection to the vendor daemon, *adskflex.exe*.

lmtools.exe

A graphical user interface utility used to administer the FLEXnet license technology. (*Lmutil.exe* is the command line version of this utility.)

lmutil.exe

A command line utility used to administer the FLEXnet license technology. (*lmtools.exe* is the graphical user interface version of this utility.)

master daemon

See [lmgrd.exe](#) on page 70.

network license

A license that allows you to run an Autodesk product with a license that is shared by various computers on a network.

network license installation

A type of installation that requires you to install and run the Network License Manager from a network server. You must install and configure the Network License Manager before clients can run the Autodesk product.

Network License Manager

The technology used by Autodesk for network license management.

Options file

The file used by FLEXnet to control license manager parameters, such as reserving licenses and creating report logs used with SAMreport-Lite.

physical address

See [host ID](#) on page 69.

redundant server

A license server configuration option in which three servers are used to administer licenses. The redundant servers share a license file and a pool of licenses. The redundant server pool remains functional as long as two of the three servers are running and communicating with each other.

report log file

A file used with FLEXnet and SAMreport-Lite. This log file provides information about network license usage. The Options file creates the report log.

single server

The Network License Manager is installed on a single server, so licensemanagement and activity is restricted to this server.

stand-alone license

A license that allows you to run an Autodesk product on a single workstation.

vendor daemon

See [adskflex.exe](#) on page 68.

workstation

A desktop computer used by an individual user on a network.

Index

A

- accessing
 - Installation and Licensing Guide 14
- activating programs 9, 24, 29
- activation code 23
- AdLM (Network License Manager) 51
- Adskflex option 62
- adskflex.exe (Autodesk vendor daemon) 38, 59
- applications
 - uninstalling 11, 14
- Autodesk License Borrowing utility 62
- Autodesk License Manager 51
- Autodesk Network License Manager 62
- Autodesk products
 - activating 24
 - borrowing network licenses for 61
 - License Transfer utility 27
 - reinstalling 31
 - using off network 61
- Autodesk vendor daemon 59

B

- borrowing licenses
 - about 61
 - reconnecting and borrowing again 61, 63
 - returning licenses 63
- borrowing periods 61
- bundled products 9

C

- certified hardware
 - accessing 14
- Commercial licenses 24, 50
- computers
 - licenses for 27

- configuring
 - license servers 54, 60
- copying
 - licenses 27, 30
- custom
 - installation 13

D

- daemons
 - license manager daemons 38
 - vendor daemons 38
 - versions of 59
- dates
 - expiration 61
 - system dates 31
- distributed license server model
 - about 36
 - license file example 42

E

- early returns of licenses 63
- Educational (EDU)/Institution
 - licenses 24, 50
- email registration 10
- Ethernet address 53
- expiration dates for licenses
 - about 61
- exporting licenses
 - about 27
 - transfer files 28

F

- faxing registration information 10
- files
 - uninstalling 11
- FLEXnet tools
 - about 57
 - Options file 60

updating 58

G

glossary
 installation 17
 licensing 67

H

hardware
 license errors and 30
hardware requirements
 Network License Manager 33
heartbeat signals 50
host IDs 53
host names 53

I

importing licenses
 about 27
 transfer files 29
Imtools.exe 62
installation
 glossary 17
 Installation wizard 6
 License Transfer utility 28
 multiple or bundled products 9
 Network License Manager 51
 networking issues 14
 registration and activation 9
 reinstalling 14
 repairing damaged installations 14
 stand-alone installation 6
 starting 10
 troubleshooting 11
 typical 13
 uninstalling 11, 14
 workflow 3
Installation wizard 6, 51
Internet
 program registration and
 activation 9

L

license borrowing
 about 61
 borrowing licenses 61
 expiration dates 61
 returning licenses 63
 third-party licensing tools 62
license files
 about 39
 additional parameters in 44
 combined products 43
 examples 41
 package examples 45
license manager daemon 38, 59
license servers
 borrowing licenses 61
 configuring 54, 60
 heartbeat signals 50
 host IDs and host names 53
 limited number of licenses 61
 management utilities 57
 models 35
 Network License Manager 51
 returning licenses 63
 stopping and restarting 57
 third-party licensing tools 62
 types of 35
License Transfer utility
 about 27
 installing 28
 transferring licenses 27
licenses
 about 37
 active 27
 assigning 37
 availability 37
 behaviors (term limits) 50, 60
 copying 30
 exporting 28
 FLEXnet tools 57
 importing 29
 issues 63
 license errors 30
 license files 39
 license servers 54

- license types 12
- moving between computers 30
- Network License Manager 51
- single-user 23
- transferring 27, 29
- troubleshooting 30
- types of 50
- licensing
 - glossary 67
- limits on number of licenses 61
- lmgrd.exe (license manager daemon) 38, 59
- lmttools.exe utility 53–54, 57, 59
- lmutil.exe utility 57, 59

M

- mailing registration information 10
- maintenance issues 14
- Microsoft Windows
 - configuring license servers 54
 - Network License Manager 33
- multi-product bundles 9

N

- network installations
 - issues 14
- network license installations
 - license behaviors 60
 - planning 33
 - tools and utilities 56
 - types of 50
- Network License Manager
 - about 51
 - assigning licenses 37
 - glossary 67
 - installing 51
 - license server models 35
 - uninstalling 56
 - upgrading 51
- network license servers
 - borrowing licenses 61
 - limited number of licenses 61
 - returning licenses 63
 - third-party licensing tools 62

- Not for Resale licenses 24, 50

O

- operating systems
 - reinstalling 31
- Options file (FLEXnet tools) 60

P

- package license files 45–48
- parameters in license files 44
- periods for licenses
 - about 61
- Permanent licenses 24, 50
- permanent transfers of licenses 27
- physical address 53
- private licenses 28
- Product Activation wizard 9, 23, 30
- product keys 9
- public licenses 28

R

- reactivating programs 30
- redundant license server model
 - about 37
 - license file example 43
 - package license files 47
- registering programs 9, 24
- reinstalling
 - operating systems 31
- removing
 - uninstalling programs 11, 14
- repairing
 - damaged installations 14
- restoring
 - damaged installations 14
- return dates for licenses
 - about 61
- returning borrowed licenses 61, 63

S

- serial number
 - updating 25
- servers 14
 - host IDs and host names 53
 - license servers 51, 54
 - stopping and restarting 57
- service pack 14
- single license server model
 - about 36
 - license file example 42
 - package license files 46
- single-user licenses 23
- software requirements
 - Network License Manager 33
- stand-alone installations
 - process 6
 - program registration and activation 9
- stand-alone licenses 23
- Student Portfolio licenses 24, 50
- system dates 31
- system requirements
 - accessing 14
 - Network License Manager 33
- system times 31

T

- TCP/IP names 53
- temporary transfers of licenses 27
- Term Extendable licenses 24, 50
- Term Non-Extendable licenses 25, 50
- third-party licensing tools 62

time

- system time 31
- time periods for licenses
 - about 61
- transfer files
 - exporting 28
 - importing 29
- transferring licenses 27
- Trial licenses 24
- trial mode 9
- troubleshooting installation 11
- troubleshooting license errors 30
- typical
 - installation 13

U

- uninstalling
 - Network License Manager 56
- uninstalling programs 11, 14
- updating
 - FLEXnet tools 58
- upgrading
 - Network License Manager 51

V

- vendor daemons 38, 59
- video cards 12

W

- Windows
 - configuring license servers 54
 - Network License Manager 33