

Autodesk Showcase 2011

Installation and Licensing Guide

Autodesk®

Copyright Notice

Autodesk® Showcase® 2011

© 2010 Autodesk, Inc. All rights reserved. Except as otherwise permitted by Autodesk, Inc., this publication, or parts thereof, may not be reproduced in any form, by any method, for any purpose.

Certain materials included in this publication are reprinted with the permission of the copyright holder.

The following are registered trademarks or trademarks of Autodesk, Inc., and/or its subsidiaries and/or affiliates in the USA and other countries: 3DEC (design/logo), 3December, 3December.com, 3ds Max, Algor, Alias, Alias (swirl design/logo), AliasStudio, AliasWavefront (design/logo), ATC, AUGI, AutoCAD, AutoCAD Learning Assistance, AutoCAD LT, AutoCAD Simulator, AutoCAD SQL Extension, AutoCAD SQL Interface, Autodesk, Autodesk Envision, Autodesk Intent, Autodesk Inventor, Autodesk Map, Autodesk MapGuide, Autodesk Streamline, AutoLISP, AutoSnap, AutoSketch, AutoTrack, Backburner, Backdraft, Built with ObjectARX (logo), Burn, Buzzsaw, CAiCE, Civil 3D, Cleaner, Cleaner Central, ClearScale, Colour Warper, Combustion, Communication Specification, Constructware, Content Explorer, Dancing Baby (image), DesignCenter, Design Doctor, Designer's Toolkit, DesignKids, DesignProf, DesignServer, DesignStudio, Design Web Format, Discreet, DWF, DWG, DWG (logo), DWG Extreme, DWG TrueConvert, DWG TrueView, DXF, Ecotect, Exposure, Extending the Design Team, Face Robot, FBX, Fempro, Fire, Flame, Flare, Flint, FMDesktop, Freewheel, GDX Driver, Green Building Studio, Heads-up Design, Heidi, HumanIK, IDEA Server, i-drop, ImageModeler, iMOUT, Incinerator, Inferno, Inventor, Inventor LT, Kaydara, Kaydara (design/logo), Kynapse, Kynogon, LandXplorer, Lustre, MatchMover, Maya, Mechanical Desktop, Moldflow, Moonbox, MotionBuilder, Movimento, MPA, MPA (design/logo), Moldflow Plastics Advisers, MPI, Moldflow Plastics Insight, MPX, MPX (design/logo), Moldflow Plastics Xpert, Mudbox, Multi-Master Editing, Navisworks, ObjectARX, ObjectDBX, Open Reality, Opticore, Opticore Opus, Pipeplus, PolarSnap, PortfolioWall, Powered with Autodesk Technology, Productstream, ProjectPoint, ProMaterials, RasterDWG, RealDWG, Real-time Roto, Recognize, Render Queue, Retimer, Reveal, Revit, Showcase, ShowMotion, SketchBook, Smoke, Softimage, SoftimageXSI (design/logo), Sparks, SteeringWheels, Stitcher, Stone, StudioTools, ToolClip, Topobase, Toxik, TrustedDWG, ViewCube, Visual, Visual LISP, Volo, Vtour, Wire, Wiretap, WiretapCentral, XSI, and XSI (design/logo).

Python is a registered trademark of Python Software Foundation.

All other brand names, product names or trademarks belong to their respective holders.

Disclaimer

THIS PUBLICATION AND THE INFORMATION CONTAINED HEREIN IS MADE AVAILABLE BY AUTODESK, INC. "AS IS." AUTODESK, INC. DISCLAIMS ALL WARRANTIES, EITHER EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE REGARDING THESE MATERIALS.

Contents

	Showcase Installation Guide	1
Chapter 1	Quick Start to Showcase Installation	3
	Introduction	3
	Prepare to Install Showcase	4
	Quick Start: Install Showcase	4
Chapter 2	Showcase Installation	7
	Stand-Alone Installation	7
	Preparing for Installation	7
	Installing and Running the Product	9
	Installation Troubleshooting	16
	General Installation Issues	16
	Networking Issues	18
	Uninstall and Maintenance Issues	19
Chapter 3	Glossary of Installation Terms	21
	Glossary	21
	Autodesk Licensing Guide	25

Chapter 4	Stand-Alone Licensing Guide	27
	Stand-alone Licensing	27
	Introduction	27
	Multi-Seat Stand-Alone License	28
	Activate Your Product	28
	Manage your Stand-Alone License	28
	Check Product Information	28
	View Product Information	29
	Save License Information as a Text File	29
	Update Your Serial Number	30
	Transfer your Stand-alone License	31
	About the License Transfer Utility	31
	Install the Autodesk Product	32
	Export a License	32
	Import a License	33
	Troubleshoot a Stand-alone License Error	35
	Hardware Changes	35
	Reinstalling an Operating System	35
	Changing the System Date and Time	36
	Distributing Software Image to Multiple Computers	36
	Stand-alone Licensing FAQs	37
	How do I switch my license from stand-alone to network or network to stand-alone?	37
Chapter 5	Network Licensing Guide	39
	Network Licensing	39
	Plan Your Network Licensing	39
	System Requirements for the Network License Manager	39
	Plan Your License Server Configuration	43
	Learn About Your License	45
	Network License Manager	58
	Install the Network License Manager	58
	Obtain a License Through autodesk.com	62
	Obtain the Server Host Name and Host ID Manually	62
	Configure a License Server	64
	Install SAMreport-Lite (Optional)	65
	Uninstall the Network License Manager	66
	Network License Tools	67
	FLEXnet Configuration Tools	68
	License Borrowing	78
	Network Licensing FAQs	81
	What is the difference between a stand-alone license and a network license?	81
	What is the benefit of using a network licensed version of the software?	82

	How do I switch my license from stand-alone to network or network to stand-alone?	82
	How do I change the license server information I entered during the installation?	84
	What is Internet Explorer used for?	84
	Where can I find more information on troubleshooting network licensing?	84
Chapter 6	Glossary of Licensing Terms	85
	Glossary	85
	Index	89

Showcase Installation Guide

Quick Start to Showcase Installation

1

Welcome to Autodesk® Showcase® 2011. This chapter gives a brief overview of installing Showcase on all supported platforms. Use this Quick Start guide if you are already familiar with installing Showcase. If you need more detailed information on installing Showcase, refer to [Showcase Installation](#) on page 7.

Introduction

The basic workflow to install Showcase on a single computer is as follows:

- 1 Complete the tasks described in [Prepare to Install Showcase](#) on page 4.
- 2 [Quick Start: Install Showcase](#) on page 4.

NOTE If you select the Network license type, enter your license server name in the field that appears. Contact your network administrator to find the name of your license server. If you are installing the Professional or Presenter version of Showcase using a network license, you will need to enable Professional or Presenter features after installation, as described in [Enable Showcase Professional or Presenter after a Network License Installation](#) on page 12.

- 3 If you will use a stand-alone license to run Showcase, see [Register and Activate Showcase](#) on page 14 for information on obtaining your license.

Prepare to Install Showcase

Before you install Showcase, ensure that you have done the following:

- See www.autodesk.com/showcase-hardware to verify system requirements.
- Locate your serial number and product key.
- Understand which license type you use (stand-alone or network).
- Close other programs.

See [Preparing for Installation](#) on page 7 for more detailed information.

NOTE Showcase is only supported on English versions of Windows.

Quick Start: Install Showcase

To install Showcase, you can follow the instructions in the Autodesk Showcase Installation wizard. This section provides a brief overview of the install steps.

If you require more detailed information, see [Install Showcase](#) on page 10.

To install Showcase

- 1 Do one of the following to open the Showcase installer:
 - If you are installing from a DVD, insert the DVD into your drive. The Autodesk Showcase installer appears. If the installer does not start automatically, double-click the `setup.exe` file on your DVD drive.
 - If you are installing from a download package, double-click the Showcase executable file that you downloaded.
- 2 Click Install Products to start the installation, then follow the instructions in the install wizard to continue.



- 3 In the **Select the Products to Install** window, select the components you want to install. These include Showcase and Autodesk DirectConnect 2011. Autodesk highly recommends that you install Autodesk DirectConnect if you do not already have it. DirectConnect is a family of data translators that lets you import CAD data into Showcase.
- 4 In the User and Product Information window, enter your name, Organization, Serial Number and Product Key, then click Next.
- 5 In the Begin Installation window, do one of the following:
 - To install Showcase with a stand-alone license and default installation options, click **Install**.
Obtain your stand-alone license later by following the steps in [Register and Activate Showcase](#) on page 14.
 - To change any installation options, for example to enter network license information or to change the default install path, select the product you want and click **Configure**.

NOTE If you select the Network license type, enter your license server name in the field that appears. Contact your network administrator to find the name of your license server. If you are installing the Professional or Presenter version of Showcase using a network license, you will need to enable Professional or Presenter features after installation, as described in [Enable Showcase Professional or Presenter after a Network License Installation](#) on page 12.

When you are finished, click Configuration Complete to return to the Begin Installation window and click Install.

A series of images displays as Showcase installs.

6 In the Installation Complete window, click Finish.

By default, Showcase is installed in the following directory: C:\Program Files\Autodesk>Showcase2011.

Showcase Installation

2

Stand-Alone Installation

The Showcase *Installation and Licensing* guide provides instructions on how to prepare, and then install Autodesk Showcase. If you have never installed the product before, you should familiarize yourself with the entire installation process and options before beginning.

For information about network-licensed versions of the program, see Choose an installation type.

Preparing for Installation

To prepare for installation, you should review the system requirements, understand administrative permission requirements, locate your Showcase serial number and product key, and close all running applications. Complete these tasks, and you are ready to begin installing Showcase.

Refer to the following sections for more information on each installation prerequisite.

Verify system requirements

The first task you need to complete is to make sure that your computer meets the minimum system requirements. If your system does not meet these requirements, problems can occur, both within Showcase and at the operating system level.

To review the requirements, see www.autodesk.com/showcase-hardware.

NOTE Showcase is only supported on English versions of Windows.

Administrative Permission Requirements

To install Showcase, you must have administrator permissions. You do not need to have domain administrative permissions. See your system administrator for information about administrative permissions.


You do not need administrator permissions to run Showcase. You can run the program as a limited user.

Locating Your Serial Number and Product Key

When you install Showcase, you are prompted for your serial number and product key in the Product and User Information page, or the option of installing the product in trial mode. You may enter your product information at any time during your trial mode period if you opt to install the product in that mode.

The serial number and product key are located on the outside of the product packaging, or in the Autodesk® Upgrade and Licensing Information email. Make sure to have these available before you install the program so that you don't have to stop in the middle of the installation.

The serial number must contain a three-digit prefix followed by an eight-digit number. The product key consists of five characters.



User and Product Information

First name:
MyFirstName

Last name:
MyLastName

Organization:
MyOrganization

I want to try this product for 30 days

I have my product information

Serial number:
123 - 12345678

Product key:
12345

The information you enter is permanently retained with the product. Because you can't change this information later without uninstalling, take care when entering the information. To review this product information later, on the InfoCenter toolbar, click the drop-down arrow next to the Help button (the question mark). Then click About - Product Information.

NOTE If you have lost your serial number or product key, contact the Autodesk Business Center (ABC) at 800-538-6401 for assistance.

Minimize the Chances of Installation Failure

The Showcase installation process may stop if some applications such as Microsoft® Outlook® or virus-checking programs are running. Close all running applications to avoid possible installation problems and data loss.

Installing and Running the Product

To use the product, you must install the product, register and activate it, and then launch it. You must have administrative permissions to install Showcase.

This section provides instructions for installing and activating Showcase for an individual user on a stand-alone computer. For information about installing network-licensed or multi-seat stand-alone versions of the program, see [Network Licensing Guide](#) on page 39.

Installing Showcase

The Showcase Installation wizard contains all installation-related material in one place. From the installation wizard, you can access user documentation, install supplemental tools, and add online support services.


- **Review the installation documentation.** It is recommended that you take the time to familiarize yourself with the complete installation process before you install Showcase. You can access information on installation from the installation wizard by selecting the *Read this Documentation* option, the *Documentation* and information links, or through the Help system. For late-breaking information, it is also recommended that you review the product *Readme*.
- For late-breaking information, it is also recommended that you review the Showcase *Readme* available at www.autodesk.com/showcase-docs.

Install Showcase

Install Showcase Using Default Settings on a Stand-Alone Computer

This installs Showcase to the default install path of *C:\Program Files\Autodesk\Showcase2011*.

- 1 Do one of the following to start the Showcase Installation wizard:
 - If you are installing from a DVD, insert the DVD into your drive. If the installer does not appear automatically, double-click the setup.exe file on your DVD drive.
 - If you are installing from a download package, double-click the Showcase executable file that you downloaded.
- 2 Click Install Products.
- 3 On the Select the Products to Install page, select your product(s). These include Showcase and Autodesk DirectConnect 2011. Autodesk highly recommends that you install Autodesk DirectConnect if you do not already have it. DirectConnect is a family of data translators that lets you import CAD data into Showcase. Click Next.
- 4 Review the Autodesk software license agreement. Click I Accept, and then click Next.
- 5 On the User and Product Information page, enter your user information, serial number, and product key. Click Next.



User and Product Information

First name:
MyFirstName

Last name:
MyLastName

Organization:
MyOrganization

I want to try this product for 30 days

I have my product information

Serial number:
123 - 12345678

Product key:
12345

WARNING After you click Next, you cannot change the information entered on this page unless you uninstall the product.

- 6 On the Begin Installation page, click Install.
- 7 On the Installation Complete page, note the directory path where you can find and read the installation log.
- 8 Click Finish.

You have successfully installed Showcase. You are now ready to register your product and start using the program. To register the product, start Showcase and follow the on-screen instructions.

See also [Register and Activate Showcase](#) on page 14.

Install Showcase Using Custom Settings on a Stand-Alone Computer

With this method, you can set Showcase to use a network license, change the install location, and customize other settings.

- 1 Do one of the following to start the Showcase Installation wizard:
 - If you are installing from a DVD, insert the DVD into your drive. If the installer does not appear automatically, double-click the setup.exe file on your DVD drive.
 - If you are installing from a download package, double-click the Showcase executable file that you downloaded.
- 2 Click Install Products.
- 3 On the Select the Products to Install page, select your product(s). These include Showcase and Autodesk DirectConnect 2011. Autodesk highly recommends that you install Autodesk DirectConnect if you do not already have it. DirectConnect is a family of data translators that lets you import CAD data into Showcase. Click Next.
- 4 Review the Autodesk software license agreement. Click I Accept, and then click Next.
- 5 On the User and Product Information page, enter your user information, serial number, and product key. Click Next.

WARNING After you click Next, you cannot change the information entered on this page unless you uninstall the product.

- 6 On the Begin Installation page, click **Configure**.
Use the wizard to configure additional installation options, such as whether to use a stand-alone or network license.

NOTE If you select the Network license type, enter your license server name in the field that appears. Contact your network administrator to find the name of your license server. If you are installing the Professional or Presenter version of Showcase using a network license, you will need to enable Professional or Presenter features after installation, as described in the next section, [Enable Showcase Professional or Presenter after a Network License Installation](#) on page 12.

- 7 (Optional) In the Installation Location and Select Preferences windows, you can set the following options, then click Next.
 - *Create the Desktop Shortcut for Showcase*. Clear the check box if you do not want to create a shortcut to the program.
 - *Create the Desktop Shortcut for Showcase - <Language>*. Clear the check box if you do not want to create a shortcut to the program.
 - *Product Install Path* - Specify the drive and location where you want to install Showcase.
- 8 On the Installation Complete page, note the directory path where you can find and read the installation log.
- 9 Click Finish.

You have successfully installed Showcase. You are now ready to register your product and start using the program. To register the product, start Showcase and follow the on-screen instructions.

See also:

- [Register and Activate Showcase](#) on page 14
- [Enable Showcase Professional or Presenter after a Network License Installation](#) on page 12

Enable Showcase Professional or Presenter after a Network License Installation

After installing Showcase Professional or Presenter with a network license, you must enable Showcase Professional or Presenter features as follows:

- 1 Navigate to the MSI file that corresponds to your system and license:

On the installation DVD:

```
\support\showcase_licenses_win32\Presenter\PRESLicense17.0.msi  
\support\showcase_licenses_win32\Professional\PROLicense17.0.msi  
\support\showcase_licenses_win64\Presenter\PRESLicense17.0.msi  
\support\showcase_licenses_win64\Professional\PROLicense17.0.msi
```

On a system where you downloaded and unpacked the installation executable:

```
C:\Autodesk\Showcase2011_32-bit\support\showcase_lic  
enses_win32\Presenter\PRESLicense17.0.msi  
C:\Autodesk\Showcase2011_32-bit\support\showcase_lic  
enses_win32\Professional\PROLicense17.0.msi  
C:\Autodesk\Showcase2011_64-bit\support\showcase_lic  
enses_win64\Presenter\PRESLicense17.0.msi  
C:\Autodesk\Showcase2011_64-bit\support\showcase_lic  
enses_win64\Professional\PROLicense17.0.msi
```

- 2 Double-click the MSI file.
- 3 Run the wizard that opens.

Installing Multiple or Bundled Products

Some Autodesk packages are comprised of multiple products or are part of multi-product bundles.

In the installation wizard, for packages containing multiple products, you can choose which products and languages you want to install. During the install process, you are informed whether a copy of the software is already installed. You are also warned if your system does not meet the minimum system requirements for the product. Each product name is displayed on its own tabbed panel; you can configure them individually.

If you purchased a package that is a multi-product bundle, such as an educational or institutional package, you may have a package that includes several Autodesk products. For these bundled packages, an Installer disc contains information for all the products in the package. The Installer disc helps you install all of the products. This includes a Readme which describes issues general to the bundle or suite.

NOTE If you are installing Showcase as part of a suite, Autodesk recommends that you refer to both the suite install guide and this install guide.

Register and Activate Showcase

The first time you start Showcase, the Product License Activation wizard is displayed. You can either activate Showcase at that time, or Try Showcase and activate it later. Until you register and enter a valid activation code for Showcase, you are operating the program in *trial mode* and the Product License Activation wizard is displayed for 30 days from the first time that you run the program.

If after 30 days of running Showcase in trial mode you have not registered and provided a valid activation code, your only option is to register and activate Showcase. You will not be able to run in trial mode after the 30 days expires. Once you register and activate Showcase, the Product License Activation wizard is no longer displayed.

The fastest and most reliable way to register and activate your product is by using the Internet. Simply enter your registration information and send it to Autodesk over the Internet. Once you submit your information, registration and activation occur quickly.

To register and activate Showcase

- 1 Click the Start menu ► Programs or All Programs ► Autodesk ► *<Showcase>* ► *<Showcase>*.
- 2 In the Showcase Product License Activation wizard, select Activate, and then click Next.
This starts the activation process.
- 3 Click Register and Activate (Get an Activation Code).
- 4 Click Next and follow the on-screen instructions.
If you do not have Internet access, or if you want to use another method of registration, you can register and activate Showcase in one of the following ways:
Email Create an email message with your registration information and send it to Autodesk.
Fax or Post/Mail Enter your registration information, and fax or mail the information to Autodesk.

Launch Showcase

Assuming that you followed all of the previous steps outlined in this installation section, you can launch Showcase and start taking advantage of its new and updated features. For more detailed information about the new features, learning videos, online Help, or Showcase services and support, see the Welcome screen after you launch the product.

You can start Showcase in the following ways:

- **Desktop shortcut icon.** When you install Showcase, an Showcase shortcut icon is placed on your desktop unless you cleared that option during installation. Double-click the Showcase shortcut icon to start the program.
- **Start menu.** On the Start menu, click Programs or All Programs ► Autodesk ► *<Showcase>* ► *<Showcase>*.
- **Location where Showcase is installed.** If you have administrative permissions, you can run Showcase in the location where you installed it. If you are a limited-rights user, you must run Showcase from the Start menu or from the desktop shortcut icon. If you want to create a custom shortcut, make sure that the Start In directory for the shortcut points to a directory where you have write permissions.

Uninstall Showcase

When you uninstall Showcase, all components are removed. This means that even if you've previously added or removed components, or if you've reinstalled or repaired Showcase, the uninstall removes all Showcase installation files from your system.

- 1 Open the Control Panel and do one of the following:
 - (Windows XP) Launch the Add or Remove Programs window.
 - (Windows 7 and Windows Vista) Select Programs or Programs and Features.
- 2 In the list of programs that appears, select Autodesk Showcase 2011 and click Uninstall or Remove.
- 3 Follow the instructions in the window that appears.

Installation Troubleshooting

This section provides solutions to installation issues and answers to commonly asked questions that may arise while installing your product(s). Additional troubleshooting information and support is also available at <http://autodesk.com/servicesandsupport>

General Installation Issues

This section outlines common issues and their solutions that may arise while performing a general install of your product(s).

How can I check my graphics card driver to see if it needs to be updated?

It is recommended that you verify and update your graphics card driver to optimize your program. Use the following procedure to identify your current graphics card driver.

To identify your graphics card driver

- 1 On the Start menu (Windows), click Settings ► Control Panel.
- 2 Click the Display icon to access the Display Properties.
In Vista, click Settings ► Control Panel ► Personalization ► Display Settings.
- 3 Open the Settings tab and click the Advanced button.
- 4 Click the Adapter tab to check the adapter type.
- 5 Click the Properties button and open the Driver tab to check driver version and see if newer drivers are available.

TIP Many newer graphic cards offer tabbed pages where you can learn more precise information about your specific graphic card. If specific tab pages are present, refer to them instead of the Adapter tab.

What is the text editor used for?

The text editor you designate during installation is used for editing text files such as PGP and CUS dictionary files while you are running your product.

What is the difference between a stand-alone license and a network license?

Stand-alone licensed products are registered and activated to an individual workstation. While the software can be installed on multiple systems in your facility, the license only allows one system to be operational. If you need to run more systems, you need to purchase more stand-alone licensed products, or consider converting to network licenses.

Network licensed products rely on the Network License Manager to keep track of software licenses. The software can be installed and run on multiple systems, up to the maximum number of licenses you've purchased. The Network License Manager "checks out" licenses until they are all in use. No further systems can run the program until a license is "checked in." If you need to run more systems, you can purchase additional licenses for the Network License Manager to maintain.

What is the benefit of using a network licensed version of the software?

Network licensed products are recommended for large drafting/design facilities, classrooms, and lab environments. The main advantage is that you can install products on more systems than the number of licenses you have purchased (for example, purchasing 25 licenses but installing on 40 workstations). At any one time, products will run on the maximum number of systems for which you have licenses. This means you get a true floating license. If software needs to be run on more systems, additional licenses can be purchased.

How do I access my documentation?

Documentation is available on the product media or as a web-based Help file. The complete Help system is installed during the product installation process. During the installation process, you can access specific installation and

licensing documentation by clicking the Read the Documentation or Documentation links in the wizards.

What is SAMreport-Lite?

SAMreport-Lite is a report generator that helps you monitor the usage of applications that use FLEXnet. SAMreport-Lite complements FLEXnet by providing a graphical user interface (GUI) from which to run usage reports. SAMreport-Lite can help you make better decisions about your software assets. For more information, see the *SAMreport-Lite User's Guide*.

Networking Issues

This section outlines common issues and their solutions with regards to performing a network installation or configuring your network license server(s).

Where do I find my server name?

When installing a network licensed product, you must specify the name of the server that will run the Network License Manager. If you don't know the server name, you can quickly find it by opening a Windows command prompt on the system that will be the Network License Manager. At the prompt, enter `ipconfig /all` and note the Host Name entry.

What is an administrative image (MSI) file?

An *administrative image* is a collection of shared file resources created during the deployment process and is used by deployments to install the program to networked workstations. Service packs (patches) can be applied to an administrative image when you create the deployment. A *.msi* file is a Microsoft Installer file.

What is the impact of selecting all products for the administrative image, and can I add products later?

If you elect to include all products in your deployment, the administrative image will be larger. You should select all products only when you create multiple deployments from this image and prefer not to use the installation

disc. If there are products you rarely or never use, and you do not expect to create additional deployments, you should only select a subset of products.

You can still create a deployment at a later date, and include additional products, but you need to create a new administrative image. You need the installation disc to do so.

Uninstall and Maintenance Issues

This section outlines common issues and their solutions with regards to adding and removing features, reinstalling or repairing your installation, and uninstalling products.

When should I reinstall the product instead of a repair?

You should reinstall your product if you accidentally delete or alter files that are required by the program. Missing or altered files adversely affect the performance of your product and cause error messages when you try to execute a command or find a file.

If an attempt to repair an installation fails, reinstalling is the next best option.

Do I need my original disc(s) to reinstall my product?

When performing a reinstall of the product, you are prompted to load your original disc(s). Installation data is cached locally on your drive and that data is reused when reinstalling.

When I uninstall my software, what files are left on my system?

If you uninstall the product, some files remain on your system such as files you created or edited (drawings or custom menus).

Your license file also stays on your workstation when you uninstall your product. If you reinstall on the same workstation, the license information remains valid and you do not have to reactivate the product.

Glossary of Installation Terms

3

Glossary

activate Part of the Autodesk software registration process, it allows you to run a product in compliance with the product's end-user license agreement.

Active Directory A directory service from Microsoft that is part of Windows 2000 and Windows 2003 Server that manages the identities and relationships that make up network environments.

administrative image A collection of shared file resources created by the deployment wizard and used by deployments to install the program to network workstations.

advertising A pull technology that notifies users of an updated software product that is available for installation. Users typically double-click a shortcut (or do a similar operation) to complete the installation of the advertised product.

deploy The process of installing an Autodesk product to one or more computers on a network.

deployment A link to a unique MST (Microsoft Transform) file that serves as a basis for an installation. Using the deployment wizard, administrators can create multiple deployments that result in different types of installations for users.

directory service A network service that identifies all resources on a network and makes them accessible to users and applications. Resources include email addresses, computers, and peripheral devices such as printers. Ideally, the directory service should make the physical network topology and protocols transparent so that a user on a network can access any resource without knowing

where or how it is physically connected. Virtually all directory services are based on the X.500 ITU standard.

group policy Microsoft server technology that provides a way to do push installations and advertising-based installations using standard Microsoft 2000 Server administration components.

installation image A deployment that consists of an MSI file, any associated transforms, additional user-specified custom files, and profile and registry settings.

language pack A set of installed files that enable the user to work in the application in the language specified by the Language Pack.

language family A set of languages (core product, plus language packs) that are distributed together, typically based on a geographic grouping.

License Transfer utility Allows you to use an Autodesk product on more than one computer without purchasing a separate license for each computer.

MSI Microsoft installer that supports a variety of parameters that can be scripted.

MSP Microsoft patch file (see patch).

MST Microsoft transform file. Modifies the components installed by the MSI file. For example, the deployment wizard creates an MST file with the settings that you specify. The deployment created by the deployment wizard uses the MST file in conjunction with the MSI file and MSIEEXEC to install the program on local workstations.

multi-seat stand-alone installation A type of installation where multiple stand-alone seats of the program are installed using a single serial number.

network license installation A type of installation where you install the program to workstations with the files and registry entries that allow the program to communicate with the Network License Manager.

partial profile A profile that contains partial registry information corresponding to a subset of the options available from the Files tab of the Options dialog box.

patch A software update to an application.

power user A user with rights to access and write to the *Program Files* folder and the *HKEY_Local_Machine* folder of the registry.

pull technology An installation technology that requires user interaction to complete the installation.

push technology An installation technology that installs files to a remote desktop without any user interaction.

scripting The process of using scripting languages such as VB Script to facilitate the deployment of software packages.

service pack Autodesk terminology for an application patch.

silent mode An installation that proceeds without any explicit user input. No dialog boxes are presented that require interaction from the user.

Autodesk Licensing Guide

Stand-Alone Licensing Guide

4

Stand-alone Licensing

A stand-alone license allows you to run an Autodesk® product on a single workstation.

Introduction

Stand-alone licensing allows you to use your Autodesk product in trial mode for a given number of days from the first time you launch the product. The number of days that a trial mode is active differs between Autodesk products. You can activate your license at any time before the trial period expires.

When you activate your product, you receive an activation code. If you activate online, your activation code is automatically retrieved from Autodesk and the product starts. Activations are also available through email, fax, phone, or the Autodesk website.

NOTE If you are installing and using an Autodesk product on both operating systems of a dual-boot operating system, you must obtain a separate activation code for each operating system.

The license file stays on your workstation when you uninstall your product. If you reinstall your Autodesk product on the same workstation, the license information is still valid. You do not have to reactivate the product.

Multi-Seat Stand-Alone License

A multi-seat stand-alone license allows you to install, register, and activate an Autodesk product on several workstations using a single serial number. Multi-seat licenses can be purchased through your Authorized Autodesk Reseller.

The Create Deployment feature in the provided installer simplifies deployment by creating a server image that you can access to install the software on your workstation. The software activates automatically when it is started for the first time and if an Internet connection is available.

NOTE To avoid activation failures, it is recommended that you use the provided installer to create the deployment server image.

For more information about multi-seat stand-alone install, see your product's installation documentation.

Activate Your Product

You can activate your Autodesk product either on startup or while you are running the product. If you cannot activate online, offline activation is available.

Manage your Stand-Alone License

Check Product Information

You can view detailed information about your Autodesk product and your product license (such as the license usage type and the license behavior), and then save this information as a text file.

License usage types

NOTE All license types are available as stand-alone and network except for the Student Portfolio license, which is available as stand-alone only.

Commercial A license for a product that was purchased commercially.

Not for Resale A license for a product that is not sold commercially.

Educational (EDU)/Institution A license designed specifically for educational institutions.

Student Portfolio A license for students who are using an Autodesk product as part of their curriculum.

License behaviors

Trial A license that allows individuals to try the product in trial mode for a specified number of days. The trial period starts the first time you launch your product. When the trial period expires, the product must be registered and activated to continue use.

Permanent Allows permanent use of an Autodesk product.

Term Extendable Allows access to an Autodesk product for a limited time. The term can be extended at any time.

Term Non-Extendable Allows access to an Autodesk product for a limited time. The term cannot be extended.

View Product Information

To view product information

- 1 Launch Showcase.
- 2 Select Help > About Showcase from the main menu bar.
- 3 In the About Autodesk Showcase window, click Product License Information.
- 4 In the Product License Information dialog box that appears, view details about your product and the product license.

NOTE Only basic license borrowing for Showcase is supported through the Borrow License button in this dialog box. For more information, see Borrow a Showcase license with sub-features.

- 5 In the Product License Information dialog box, click Close.

Save License Information as a Text File

You can save your product license information as a text file.

To save license information as a text file

- 1 Launch Showcase.
- 2 Select Help > About Showcase from the main menu bar.
- 3 In the About Autodesk Showcase window, click Product License Information.
- 4 In the Product License Information dialog box, click Save As.
- 5 In the Save As dialog box, name the file, choose a location where you want to save the file, and then click Save.
- 6 In the Product License Information dialog box, click Close.

Update Your Serial Number

If you installed your product with the trial serial number (000-00000000), you can update that trial serial number with a valid serial number. Your valid serial number is located on the outside of the product packaging or in the *Autodesk Upgrade and Licensing Information* email you received if you downloaded your product.

NOTE If you have lost your serial number, contact the Autodesk Business Center (ABC) at 800-538-6401 for assistance.

When you register and activate your product, you are asked for the product serial number, which is automatically entered upon completion of the activation process.

If you have a multi-product bundle of software that uses a single serial number, only the first product you register and activate displays the updated serial number. For other products to display the serial number, you must update it from the Help menu.

NOTE For the updated serial number to display, you must be logged into the system with Administrator rights.

To update your serial number

- 1 Launch Showcase.
- 2 Select Help > About Showcase from the main menu bar.

- 3 In the About Autodesk Showcase dialog box that appears, click Product License Information.
- 4 In the Product License Information dialog box, click Update.
- 5 In the Update the Serial Number dialog box, enter your product serial number.
The serial number is located on the outside of the product packaging or in the *Autodesk Upgrade and Licensing Information* email you received if you downloaded your product.

NOTE If you have lost your serial number, contact the Autodesk Business Center (ABC) at 800-538-6401 for assistance.

- 6 Click OK. You can now see the updated serial number.

Transfer your Stand-alone License

About the License Transfer Utility

The License Transfer Utility transfers a product license online from one computer to another, and ensures that the product works only on the computer that contains the license. The License Transfer Utility is a custom stand-alone installation option. During installation, a shortcut is created. A shortcut is installed once per product, per workstation.

You may want to transfer a license to a computer temporarily (if you want to use an Autodesk product on your laptop, for example) or permanently (if the computer where you originally activated your Autodesk product is being replaced). You can leave the license on the secondary computer indefinitely, or you can move the license between computers as needed.

License transfers rely on the product's serial number. Before an Autodesk product can be exported, it must be activated with the serial number and product key. During license import, a previously activated and exported license is imported to a product or product suite installed with the same serial number. The activation is transferred to the import computer, completing the license transfer.

NOTE The number of concurrent exports you can have, is equal to the number of seats you own. For example, if you own one seat you can have one export in progress at a time. You cannot complete another export until the one in progress has been imported. Similarly, if you have five seats, you can have up to five concurrent exports in progress at one time.

NOTE When you upgrade your Autodesk product (non-subscription), you can no longer perform online license transfers of the previous license.

NOTE Although the License Transfer Utility allows you to transfer your product license between computers, your license agreement may not allow the installation of an Autodesk product on more than one computer. Read your license agreement to find out whether your product license permits the use of the License Transfer Utility.

To transfer a license you must have an Internet connection, have an Autodesk product installed on both computers, and perform an online export and import of the license.

Install the Autodesk Product

Before you can use the License Transfer Utility to transfer licenses, you must have an Autodesk product installed on all computers involved in the transfer.

To install the Autodesk product

- 1 Install and activate the Autodesk product on a computer.
See your product's installation instructions for complete details.
- 2 Install the Autodesk product on any other computer that will be using the License Transfer Utility. You do not have to register or activate the product on this computer.
See your product's installation instructions for complete details.

Export a License

A license is exported when the License Transfer Utility moves a product license from a computer to the online Autodesk server.

The license can be exported as public or private. Exporting a license as public means that you are not reserving the license and anyone using the same serial

number and their own user ID and password can import that license. Exporting a license as private means that you are reserving that license for yourself and the license can only be imported with the same serial number, your user ID, and your password.

NOTE An Internet connection is required to export a license.

To export a license

- 1 On the computer where you want to export the license, do the following:
 - (Windows XP/Windows 7/Windows Vista) Click Start ► All Programs
 - Autodesk ► *[Autodesk Product]* ► License Transfer Utility.

The License Transfer Utility displays the Autodesk product name and serial number.

- 2 In the License Transfer Utility, click Sign In.
- 3 On the Log In page, enter your Autodesk user ID and password and click Log In.
- 4 On the License Export page, confirm the export information.
- 5 If you want to make the license available as a public import, click Make the license available as a public import.
- 6 Click Export.
- 7 On the License Export Confirmation page, click Finish.

Import a License

A license is imported when the License Transfer Utility moves a previously exported product license from the online Autodesk server to a computer.

When you have exported a product license from a computer, you complete the license transfer process by importing that license onto a computer. A license is imported when the License Transfer Utility creates an active license on a computer, allowing your Autodesk product to run on this computer.

When you use the License Transfer Utility to import a license to a computer, you are not activating the product on the computer; you are simply transferring your activation to this machine.

NOTE An Internet connection is required to import a license.

To import a license

- 1 On the computer where you want to import the license, do the following:
 - (Windows XP/Windows 7/Windows Vista) Click Start ► All Programs ► Autodesk ► *[Autodesk Product]* ► License Transfer Utility.

The License Transfer Utility displays the Autodesk product name and serial number.

- 2 In the License Transfer Utility, click Sign In.
- 3 On the Log In page, enter your Autodesk user ID and password and click Log In.
- 4 On the License Import Confirmation page, click Finish.

The license is now imported to the computer and you can run your Autodesk product on this computer. If you want to transfer the license to another computer, repeat the export and import procedures.

To import a license to replace a trial license

- 1 On the computer where you want to import the license, do the following:
 - (Windows XP/Windows 7/Windows Vista) Click Start ► All Programs ► Autodesk ► *[Autodesk Product]* ► License Transfer Utility.

The License Transfer Utility displays the Update the Serial Number and Product Key options.

- 2 Enter the serial number and product key to update your Autodesk product and click Update.

The License Transfer Utility displays the updated serial number.
- 3 In the License Transfer Utility, click Sign In.
- 4 On the Log In page, enter your Autodesk user ID and password and click Log In.
- 5 On the License Import Confirmation page, click Finish.

The license is now imported to the computer and you can run your Autodesk product on this computer. If you want to transfer the license to another computer, repeat the export and import procedures.

Troubleshoot a Stand-alone License Error

Hardware Changes

If you replace or reconfigure hardware on the computer where your Autodesk product license resides, the stand-alone license might fail. You will not be able to use your product.

To prevent damage to your product license, use the License Transfer Utility to export your license file. After you make the hardware change, you can import the license file back. For instructions about using the License Transfer Utility, see [Transfer Your Stand-Alone License](#).

NOTE If you get a license error when you change your hardware, you may have to reactivate your license. See [Activate Your Product](#) on page 28.

Reinstalling an Operating System

If you reinstall your operating system on the computer where your Autodesk license resides, the license might fail. You will not be able to use your product.

To resolve a license error in this case, you must reactivate your product. See [Activate Your Product](#) on page 28.

To prevent a license error when you reinstall an operating system

NOTE If using Norton Ghost™ or another image utility, do not include the Master Boot Record.

- 1 Locate one of the following folders and make a backup copy:
 - (Windows XP) C:\Documents And Settings\All Users\Application Data\FLEXnet
 - (Windows 7/Windows Vista) C:\ProgramData\FLEXnet
- 2 Reinstall the operating system and reinstall the Autodesk product.
- 3 Paste the license folder to the same location from which you originally copied the folder in step 1.
You can now run your Autodesk product.

Changing the System Date and Time

Your product license allows for time changes to the system clock within two days of the current time. If you set your system clock back more than two days, the next time you start your product, you will receive a message that gives you the option of correcting the system clock. If you do not correct the system clock, you receive a license error.

To prevent a license error due to a change in system date and time

- Make sure that your computer's system date and time are accurate when you install and activate your Autodesk product.

Distributing Software Image to Multiple Computers

You can use the Deployment Wizard's Stand-alone option to create a software installation image on your server. You can distribute this image by making it available on your computer network. During creation of this image, you are prompted for registration information, which is stored with the image and deployed to all installations.

Additionally, you can manually distribute the software using the installation CD that comes with your Autodesk product. However, if your computers do not have an Internet connection, make sure the registration data for each computer matches exactly. Inconsistent registration data can cause activation failures.

To prevent a license error when distributing software image to multiple computers

- The distribution of applications using "ghosting" is not recommended, and can result in incomplete installations and activation problems.

Stand-alone Licensing FAQs

How do I switch my license from stand-alone to network or network to stand-alone?

If you have purchased stand-alone and network licenses and you want to switch which license Showcase is using, there are two main methods to change the license type.

- Uninstall and re-install Showcase, changing the type of license you specify during the install.
- Edit the `SHOWCASE_LICENSE_METHOD` environment variable in your `license.env` file.
If you have added the `SHOWCASE_LICENSE_METHOD` variable to your system environment variables or to a `Showcase.env` file, you must also update the license type in those locations.

To edit the `SHOWCASE_LICENSE_METHOD` environment variable

- 1 Locate the `license.env` file in the following location:
 - (Windows) `C:\Program Files\Autodesk\Showcase2011\bin`
- 2 Edit the `SHOWCASE_LICENSE_METHOD` variable to indicate the type of license you want, for example:
`SHOWCASE_LICENSE_METHOD=standalone`
to set Showcase to use a stand-alone license, or
`SHOWCASE_LICENSE_METHOD=network`
to set Showcase to use a network license.
If you are switching from a stand-alone to a network license, continue with the following steps to set your license server name.
- 3 Navigate to the following directory to locate and open the `LICPATH.LIC` file.
 - (Windows) `C:\Program Files\Autodesk\Showcase2011`
- 4 Edit the line `SERVER <servername>` where `<servername>` is your license server name.

If you do not find the `LICPATH.LIC` file in this location, you can create a license file by saving a text file with the extension `.lic`, and including the following lines:

```
SERVER <servername> 0  
USE_SERVER
```

IMPORTANT If you have added the `SHOWCASE_LICENSE_METHOD` variable to your system environment variables or to a `Showcase.env` file, you must also update the license type in those locations.

The `Showcase.env` file is found in `C:\Documents and Settings\user\My Documents\showcase`.

To locate the `Showcase.env` file

- Go to `C:\Documents and Settings\user\My Documents\showcase`

To set the variable in the environment

- From the Control Panel, double-click System to open the System Properties, then switch to the Advanced tab and click Environment Variables.

Network Licensing Guide

5

Network Licensing

A network license lets you run an Autodesk product on a network. Network licenses can be purchased through your Authorized Autodesk Reseller.

Setting up network licenses for an Autodesk product requires careful planning and execution. This section gives you instructions about how to set up a network licensed environment, and assumes that you are familiar with the terminology and processes required to set up an Autodesk product to run on a network.

Plan Your Network Licensing

This section contains information that you need to know before you set up a network license server. The section includes information about supported license server models, license operation and availability, network license file definitions and parameters, license file examples, license types and behaviors, and the license server heartbeat signal.

System Requirements for the Network License Manager

System Requirements for the Network License Manager (Windows)

Make sure that your network license server meets the minimum recommended requirements. See the following tables for hardware and software requirements.

NOTE The Network License Manager supports Ethernet network configurations only.

Hardware and software requirements for the network license server (Windows)

Hardware/Software	Requirement
Operating System	Windows® 7® 32-bit Windows 7 64-bit
	<ul style="list-style-type: none">■ Windows 7 Starter (32-bit)■ Windows 7 Home Basic (32-bit)■ Windows 7 Home Premium■ Windows 7 Professional■ Windows 7 Ultimate■ Windows 7 Enterprise
	Windows Vista 32-bit SP2 or later Windows Vista 64-bit SP2 or later
	<ul style="list-style-type: none">■ Windows Vista Enterprise■ Windows Vista Business■ Windows Vista Ultimate■ Windows Vista Home Premium and Basic (32-bit)■ Windows Vista Home Premium (64-bit)
	Windows XP 32-bit SP2 or later Windows XP 64-bit SP2 or later
	<ul style="list-style-type: none">■ Windows XP Home■ Windows XP Professional
	Windows Server 32-bit SP1 or later Windows Server 64-bit SP1 or later
	<ul style="list-style-type: none">■ Windows 2008 Server R2■ Windows 2008 Server■ Windows 2003 Server R2■ Windows 2003 Server

Hardware and software requirements for the network license server (Windows)

Hardware/Software	Requirement
Computer/processor	Intel® Pentium® III or higher 450 Mhz (minimum)
Network interface card	Compatible with existing Ethernet network infrastructure NOTE The Network License Manager supports multiple network interface cards, but at least one must be an Ethernet card.
Communication protocol	TCP/IP NOTE The Network License Manager uses TCP packet types.
Browsers	Internet Explorer® 6 Internet Explorer 7 Internet Explorer 8
FLEXnet	11.7.0.0

Virtual Machine Support (Windows)

Hardware	Virtualizer	Virtual OS
Intel PC 64	Windows 2008 or Windows 2003R2 servers running on VMware® ESX3.5 Update 3 (License Manager Only)	Vista 64-bit, Vista 32-bit, Windows XP 32-bit, Windows 7 32-bit (Home Premium, Professional, Ultimate, and Enterprise), Windows 7 64-bit, Windows Server 32-bit, Windows Server 64-bit

System Requirements for the Network License Manager (Mac OS X)

Make sure that your network license server meets the minimum recommended requirements. See the following tables for hardware and software requirements.

NOTE The Network License Manager supports Ethernet network configurations only.

Hardware and software requirements for the network license server (Mac OS X)

Hardware/Software	Requirement
Operating system	Mac OS® X version 10.6 and later
Computer/processor	Intel Mac
Network interface card	Compatible with existing Ethernet network infrastructure NOTE The Network License Manager supports multiple network interface cards, but at least one must be an Ethernet card.
Communication protocol	TCP/IP NOTE The Network License Manager uses TCP packet types
Browsers	Safari 4.0
FLEXnet	11.7.0.0

System Requirements for the Network License Manager (Linux)

Make sure that your network license server meets the minimum recommended requirements. See the following tables for hardware and software requirements.

NOTE The Network License Manager supports Ethernet network configurations only.

Hardware and software requirements for the network license server (Linux)

Hardware/Software	Requirement
Operating system	Linux® 64-bit Red Hat® Enterprise Linux 5.0 WS (U4)
Computer/processor	Intel Pentium 3 or higher 450 Mhz (minimum)
Network interface card	Compatible with existing Ethernet network infrastructure

Hardware and software requirements for the network license server (Linux)

Hardware/Software	Requirement
	NOTE The Network License Manager supports multiple network interface cards, but at least one must be an Ethernet card.
Communication protocol	TCP/IP NOTE The Network License Manager uses TCP packet types
FLEXnet	11.7.0.0

Plan Your License Server Configuration

You must decide which license server model to use for managing your Autodesk product licenses on a server. Autodesk supports the following network license server models:

- Single license server model
- Distributed license server model
- Redundant license server model

Single License Server Model

In the single license server model, the Network License Manager is installed on a single server, so license management and activity is restricted to this server. A single license file represents the total number of licenses available on the server.

Advantages of the Single License Server Model

- Because all license management takes place on a single server, you have just one point of administration and one point of failure.
- Of the three license server models, this configuration requires the least amount of maintenance.

Disadvantage of the Single License Server Model

- If the single license server fails, the Autodesk product cannot run until the server is back online.

Distributed License Server Model

In the distributed license server model, licenses are distributed across more than one server. A unique license file is required for each server. To create a distributed license server, you must run the Network License Manager on each server that is part of the distributed server pool.

Advantages of the Distributed License Server Model

- Servers can be distributed across a wide area network (WAN); they do not need to exist on the same subnet.
- If one server in the distributed server pool fails, the licenses on the remaining servers are still available.
- If you need to replace a server in the distributed server pool, you do not need to rebuild the entire pool.
- Server replacement is easier than in a redundant server pool, where you must reactivate the entire pool.

Disadvantage of the Distributed License Server Model

- If a server in the distributed server pool fails, the licenses on that server are unavailable.

Redundant License Server Model

In the redundant license server model, you use three servers to authenticate a single license file. One server acts as the master, while the other two provide backup if the master server fails. With this configuration, licenses continue to be monitored and issued as long as at least two servers are still functional. The license file on all three servers is the same. You must install the Network License Manager on each server.

In the redundant license server model, all servers must reside on the same subnet and have consistent network communications. (Slow, erratic, or dial-up connections are not supported.)

Advantage of the Redundant License Server Model

- If one of the three servers fails, all licenses that are managed in the server pool are still available.

Disadvantages of the Redundant License Server Model

- If more than one server fails, no licenses are available.
- All three servers must reside on the same subnet and have reliable network communications. The redundant server pool does not provide network fault tolerance.
- If one of the three servers is replaced, the complete redundant server pool must be rebuilt.
- If your Autodesk product supports license borrowing and licenses are borrowed from a redundant license server pool, you must restart the license server after you stop the Network License Manager.

Learn About Your License

In this section, you learn about license operation and availability, the license file, license types and behaviors, and the heartbeat signal.

License Operation and Availability

When you start an Autodesk product, the product determines the server from which it should try to obtain a license. The product then requests a license through the TCP/IP network protocol to the license server.

If the number of available licenses has not been exceeded on the license server, the Network License Manager assigns a license to the workstation. A product session then starts on the workstation, and the number of available licenses on the license server is reduced by one.

Likewise, when you exit a product, the Network License Manager frees a license for another user. If you run multiple sessions of an Autodesk product on an individual workstation, only one license is used. When the last session is closed, the license is freed.

The following three processes manage the distribution and availability of licenses:

- **License manager daemon** (*lmgrd.exe*). Handles the original contact with the application, and then passes the connection to the vendor daemon. The *lmgrd.exe* daemon is used to communicate with the vendor daemon only; *lmgrd.exe* does not authenticate or dispense licenses, but rather passes user requests to the vendor daemon. By using this approach, a single *lmgrd.exe* daemon can be used by multiple software vendors to provide license authentication. The *lmgrd.exe* daemon starts and restarts the vendor daemons as needed.
- **Autodesk vendor daemon** (*adskflex.exe*). Tracks the licenses that are checked out and the workstations that are using them. Each software vendor has a unique vendor daemon to manage vendor-specific licensing. As its name implies, the *adskflex.exe* vendor daemon is specific to Autodesk products.
- **License file**. A text file that has vendor-specific license information.

You can run only one Autodesk vendor daemon (*adskflex.exe*) on your license server. This means that if you plan to serve licenses for multiple Autodesk products that were purchased individually (not as part of a suite or bundle) you must combine the license file contents for the products into one license file.

For example, if you plan to serve Showcase licenses from a machine that is already serving 3ds max licenses, you must append the contents of your Showcase license file to the 3ds max license file. See [Example of a License File for Combined Autodesk Product Versions](#) on page 51 for more information.

TIP You can use the following commands to query the status of your license server and determine how many licenses you have in total, how many are in use, and to verify that your license server is up and running:

- (Windows) `lmutil lmstat -a -c <license file>` (where *<license file>* is your license file name)
 - (Mac OS X)
`/usr/local/flexnetserver/lmutil lmstat -a -c /var/flexlm/showcase.lic`
 - (Linux)
`/opt/flexnetserver/lmutil lmstat -a -c /var/flexlm/showcase.lic`
-

License Files

The network license file you receive from Autodesk contains licensing information required for a network installation. You obtain license file data when you register your Autodesk product.

The license file contains information about network server nodes and vendor daemons. It also contains an encrypted digital signature that is created when Autodesk generates the file.

The license file is located on your license server in the location that you specify when you save the license file from the RegisterOnce Web page, or using the license information that Autodesk emails to you.

NOTE If you are already running a network license server for a separate Autodesk product, such as 3ds max, you must append the contents of your Showcase license file to the contents of the license file for the other Autodesk product. See [Example of a License File for Combined Autodesk Product Versions](#) on page 51.

The following table defines each license file parameter.

Definitions of license file parameters			
Line	Parameter	Definition	Example
SERVER	Host Name	Host name of the server where the Network License Manager resides	LABSERVER
	Host ID	Ethernet address of the server where the Network License Manager resides	03D054C0149B
USE_SERVER	[None]		
VENDOR	Vendor Daemon	Name of the server-side Autodesk vendor daemon	<i>adskflex.exe</i>
	Port Number	Network port number reserved and assigned for use only by Autodesk products running the Autodesk vendor daemon	port=2080
PACKAGE	Name	Name of feature code group	<i>SERIES_1</i>
	Version	Internal version number reference	1.000

Definitions of license file parameters			
Line	Parameter	Definition	Example
	COMPONENTS	List of feature codes supported in the package	COMPONENTS= "526000REVIT_9_OF\ 51200ACD_2007_OF\ 513001IN- VBUN_11_OF"
	OPTIONS		OPTIONS=SUITE
	SUPERSEDE	Replacement for any existing Increment line of the same feature code from any license files on the same license server that have a date earlier than the defined Issue Date	SUPERSEDE
	SIGN	Encrypted signature used to authenticate the attributes of the license file	SIGN=0 SIGN2=0
INCREMENT	Feature Code	Product supported by the license file	51200ACD_2007_OF
	Expiration Date	Amount of time the licenses are available	permanent
	Number of Licenses	Number of licenses supported by the license file	25
	VENDOR_STRING	License usage type and license behavior of the product that is supported by the license file	COMMERCIAL
	BORROW	Definition of the license borrowing period for the licenses defined under the same increment line. In this example, the maximum period that licenses can be borrowed is 4320 hours (180 days), unless otherwise noted (for example, BORROW=2880 means that licenses can be borrowed for a maximum of 2880 hours, or 120 days).	BORROW=4320

Definitions of license file parameters

Line	Parameter	Definition	Example
		License borrowing is disabled when this parameter is absent in the license file.	
	DUP_GROUP	Definition of multiple license requests when the same user and same host share the same license	DUP_GROUP=UH
	ISSUED	Date that the license file was generated by Autodesk	15-jul-2006
	Serial Number	Serial number of the Autodesk product	123-12345678
	SIGN	Encrypted signature used to authenticate the attributes of the license file	SIGN=6E88EFA8D44C

License File Examples

Example of a License File Not Specific to a Product

Here is an example of the contents of a license file and the parameters associated with each line:

```
SERVER ServerName HostID
USE_SERVER
VENDOR adskflex port=portnumber
INCREMENT feature_code Adskflex Version ExpDate NumberofLicenses
\
VENDOR_STRING=UsageType:Behavior BORROW=4320 SUPERSEDE \
DUP_GROUP=DupGrp ISSUED=IssueDate SN=SerialNumber SIGN= \
```

Example of a License File for a Single or Distributed Server

Here is an example of a completed license file for a single or distributed license server model:

```
SERVER XXHP0528 0019bbd68993
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 57600ACD_2009_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1393 \
  E368 816E D417 C1CD 7DBD 7B90 1354 D6F0 48FE EBB8 9C84 C3AF \
  7D79 BEE1 0181 0655 76FF 996C B707 14B5 D4DE A3FE 0B2D 2D36 \
  057C A579 7866 26BF 44E2" SIGN2="1280 943B 53A7 9B93 E00B D967
  \
  D821 BD37 BE6D B78A F074 B223 88AA 242C DD0A 1292 D56F 4108 \
  62CD FA35 E365 0736 A011 7833 8B35 7BFF DAD8 34A8 452F 2EB4"
```

Example of a License File for a Redundant Server

Here is an example of a completed license file for a redundant license server model:

```
SERVER CCN12378042 001cc4874b03 27005
SERVER XXHP0528 0019bbd68993 27005
SERVER CCN12378043 001cc4874b10 27005
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 57600ACD_2009_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=10-Jan-2008 SN=123-12345678 SIGN="11C4 \
  CA79 07FC 7AD0 409A 6E04 6E98 D76C 197C 0416 076C B211 1CDD \
  D0AB 698B 16BF 7A0E D4F8 1CFE 2985 644F 64CD CECE 0DDB 5951 \
  3262 7C31 13A8 F08F 55B2" SIGN2="19A6 FDA3 2ED5 5301 8675 7B81
  \
  1B0E 451B 19F1 1A99 C8E9 CBA6 8CB3 6AC3 8B38 1519 13F2 2373 \
  82AE 55E5 1A25 4952 4458 F3A2 6F28 D25D 1DC0 E066 209B 0953"
```

NOTE The redundant server model requires the addition of a port number (the default is 27005) for each server.

Example of a License File for Combined Autodesk Product Versions

You can combine a license file for different releases of the same Autodesk product or for different Autodesk products, and run all products from one license server. For example, you can combine a license file for AutoCAD 2009 with license files for Autodesk Maya® 2009 and AutoCAD Map.

If your license server distributes licenses for multiple Autodesk products that were purchased individually (not part of a suite or bundle), you must combine the network license information from all products into one license file.

In this example, the content from a license file for AutoCAD 2008 has been appended to an AutoCAD 2009 license file:

```
SERVER XXHP0528 0019bbd68993
USE_SERVER
VENDOR adskflex port=2080
INCREMENT 57600ACD_2009_0F adskflex 1.000 permanent 5 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1393 \
  E368 816E D417 C1CD 7DBD 7B90 1354 D6F0 48FE EBB8 9C84 C3AF \
  7D79 BEE1 0181 0655 76FF 996C B707 14B5 D4DE A3FE 0B2D 2D36 \
  057C A579 7866 26BF 44E2" SIGN2="1280 943B 53A7 9B93 E00B D967 \
  D821 BD37 BE6D B78A F074 B223 88AA 242C DD0A 1292 D56F 4108 \
  62CD FA35 E365 0736 A011 7833 8B35 7BFF DAD8 34A8 452F 2EB4"
INCREMENT 54600ACD_2008_0F adskflex 1.000 permanent 3 \
  VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
  DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1E6E \
  4B61 5712 4766 92A0 6782 9EF4 3F47 56A1 1F38 6DE8 C0C7 90AC \
  7289 152E 0EA2 CC0D 3F10 577A 0489 CEB6 10D5 FBCC B552 0C9D \
  5966 91A6 59F0 2788 FACE" SIGN2="1DDF 3B9D 3392 71D5 AB08 7E05 \
  8497 111E 092F 0E54 8DC2 2BED 17C2 2CC1 981B 0EC2 BC15 8F00 \
  C79A ABFD 2136 BABA 2EDF E941 EA53 32C6 597F F805 5A8A 599A"
```

For example, the section of license information you need to append from one file into the other is similar to the following:

```
INCREMENT 54600ACD_2008_0F adskflex 1.000 permanent 3 \  
VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \  
DUP_GROUP=UH ISSUED=09-Jan-2008 SN=123-12345678 SIGN="1E6E \  
4B61 5712 4766 92A0 6782 9EF4 3F47 56A1 1F38 6DE8 C0C7 90AC \  
7289 152E 0EA2 CC0D 3F10 577A 0489 CEB6 10D5 FBCC B552 0C9D \  
5966 91A6 59F0 2788 FACE" SIGN2="1DDF 3B9D 3392 71D5 AB08 7E05 \  
8497 111E 092F 0E54 8DC2 2BED 17C2 2CC1 981B 0EC2 BC15 8F00 \  
C79A ABFD 2136 BABA 2EDF E941 EA53 32C6 597F F805 5A8A 599A"
```

Package License File Examples

Autodesk offers a package license file option, which allows you use of a set of products that are packaged and sold together. The package license file contains a set number of licenses for four different versions of your software. Running an instance of any one of the versions uses one license in the package. Packaged license files support prior versioning for subscription users. Package license files operate under the following guidelines:

- Package license files come with the current version of the software and three previous versions of the same product.
- License files may be combined with license files for different products. For more information about combining license files, see [Example of a Package License File for Combined Autodesk Product Versions](#) on page 55.
- Package license files cannot be combined with non-package license files for product versions contained in the package. For example, you cannot combine a *Autodesk Product 2009* package license file with a regular license file for *Autodesk Product 2008*, *2007*, or *2006*.
- Both the PACKAGE and INCREMENT sections of the license are required for licensing to work properly. When you combine license files, be sure to include both of these sections.
- License borrowing, option files, and licensing cascading work the same for package licenses as they do for regular license files.
- A new license file will supersede an older license file.

The following sections provide package license file examples for single, distributed, and redundant license servers, and combined Autodesk product versions.

Example of a Package License File for a Single or Distributed Server

Here is an example of a completed license file for a single or distributed license server model:

```
SERVER Server1 1a34567c90d2
USE_SERVER
VENDOR adskflex port=2080
PACKAGE SERIES_1 adskflex 1.000 COMPONENTS="54700REVIT_2009_0F \
54600ACD_2009_0F 51300INVBUN_11_0F" OPTIONS=SUITE SUPERSEDE \
ISSUED=09-Jan-2008 SIGN="1707 9EAC CBCB 2405 692E 4A89 \
AA26 30CC 2AC2 D6B3 A61B AB5E 492E 3EBD 0B48 4E75 193A DA82" \
FC45 C009 E360 944A 14BA E99C 9B24 5A1B 4A44 083A BE5F 3827 \
SIGN2="004A FC90 AB47 3F6B 59BC 0E6D 6681 6971 A76A BA52 98E2
\
5671 26B3 0E78 791B 109F 0591 7DC3 F09F 4D8D 4FB7 E341 4A03 \
CD68 1D77 27F8 8555 9CF7 DEDD 9380"
INCREMENT SERIES_1 adskflex 1.000 permanent 100 \
VENDOR_STRING=commercial:permanent BORROW=4320 DUP_GROUP=UH \
SUITE_DUP_GROUP=UHV SN=123-12345678 SIGN="1707 9EAC CBCB \
692E 4A89 FC45 C009 E360 944A 14BA E99C 9B24 5A1B 4A44 BE5F \
3827 AA26 30CC 2AC2 D6B3 A61B AB5E 492E 3EBD 0B48 DA82" \
SIGN2="004A FC90 AB47 3F6B 59BC 0E6D 6681 6971 A76A BA52 \
5671 26B3 0E78 791B 109F 0591 7DC3 F09F 4D8D 4FB7 E341 4A03 \
CD68 1D77 27F8 8555 9CF7 DEDD 9380"
```

Example of a Package License File for a Redundant Server

Here is an example of a completed license file for a redundant license server model:

```
SERVER 1a34567c90d2 27005
SERVER 2a34567c90d2 27005
SERVER 3a34567c90d2 27005
USE_SERVER
VENDOR adskflex port=2080
PACKAGE 64300ACD_F adskflex 1.000 COMPONENTS="57600ACD_2009_OF \
54600ACD_2008_OF 51200ACD_2007_OF 48800ACD_2006_OF" \
OPTIONS=SUITE SUPERSEDE ISSUED=27-May-2008 SIGN="1092 05D8 \
A206 276B 2C84 EFAD ACA5 C54B 68A4 653E C61F 31DE C8CE B532 \
CFBB 0006 5388 347B FDD6 A3F4 B361 7FD4 CDE4 4AAC 0D11 B0EF \
4B44 BFD6 3426 97DD" SIGN2="0670 B01A D060 0069 FF25 F1CD D06B
\
314E E7C9 3552 5FFA 4AC7 28A7 C897 F56A 19BB FB1C 754E 6704 \
DEEA AC4E F859 2E9B 64B6 0DD0 9CCE 9556 269F EAC0 2326"
INCREMENT 64300ACD_F adskflex 1.000 permanent 50 \
VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
DUP_GROUP=UH SUITE_DUP_GROUP=UHV ISSUED=27-May-2008 \
SN=399-99999999 SIGN="1B5B 8D70 4CAD 32E5 9CA2 82E0 5C47 291C
\
35AB 9B9C 5B3E 5067 F61B 4139 1B32 0716 1FD3 5105 A991 B78E \
9D1E 63AB BC23 0D1E B70C 2A05 E1C1 F605 ABB1 2EA8" SIGN2="01D6
\
31F5 2951 4500 E5C8 058F 7490 9789 9EF4 CBED DA27 5F06 6780 \
9033 2018 0C3B E1E0 3580 E60E C2BB B4AB 8D6A 4245 3059 8CA6 \
2EFE DFAE 027F 2ABE 3F2B"
```

Example of a Package License File for Combined Autodesk Product Versions

Here is an example of a completed license file for combined Autodesk product versions:

```

SERVER servername 123456789111
USE_SERVER
VENDOR adskflex port=2080
PACKAGE 64300ACD_F adskflex 1.000 COMPONENTS="57600ACD_2009_0F \
54600ACD_2008_0F 51200ACD_2007_0F 48800ACD_2006_0F" \
OPTIONS=SUITE SUPERSEDE ISSUED=25-Jun-2008 SIGN="03EF DE18 \
8046 0124 4EA4 6953 F82D 3169 7C24 D0DE E58E 8168 FFA3 D891 \
B43B 08D8 7E7F C6ED CBCC FE2A BB0A 4566 C2AE F1C1 D373 8348 \
E6E3 884A E398 1C78" SIGN2="07AC D696 8844 D19F AB00 8B75 53A3
\
2F76 91DF AED0 3231 1506 0E6B ADC6 C3B8 1797 93B5 9756 8C0F \
8811 56E6 B2BA 0523 FE2E 82B7 1628 076F 173B F37C 7240"
INCREMENT 64300ACD_F adskflex 1.000 permanent 2 \
VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
DUP_GROUP=UH SUITE_DUP_GROUP=UHV ISSUED=25-Jun-2008 \
SN=399-99999999 SIGN="1CCB E88D B819 8604 06FA 9AEE 42F1 CBEA
\
37B9 3CFA A0A8 697F 9CB1 8354 6256 05ED 69D4 D2FF D512 6A2E \
D5DD B722 EF5B 3172 BA95 4625 F8D3 DD24 BB39 6A58" SIGN2="0DFE
\
FA6F C378 20E0 2622 BE52 B434 F99F 2681 2B93 64F2 CE0C 7F4A \
7024 B3D1 051A 6920 72BD DE35 8920 E6A1 C8D6 AF23 7BE7 CC91 \
6916 70B1 9E80 AB07 1644"
PACKAGE 64800INVPRO_F adskflex 1.000 \
COMPONENTS="59600INVPRO_2009_0F \
55300INVPRO_2008_0F 51400INVPRO_11_0F 49000INVPRO_10_0F" \
OPTIONS=SUITE SUPERSEDE ISSUED=25-Jun-2008 SIGN="1306 5990 \
F8A1 56FB 1D8A 9DA7 D6AE 8E9E F6EC 2862 367A 36E2 C5FB E6E1 \
4AAA 0128 8C2D 95FD 09B2 ABA1 6F98 A0A3 70DE 3220 6835 7E51 \
3849 9D81 8BDC 9DC1" SIGN2="0021 AA08 F2E7 8AEB 5345 341A 7E42
\
3001 B8C5 DFC2 6EB8 87C5 C04A AE43 A10F 1DA1 EF8A F0FA 10F5 \
AC81 1E22 789F A18D 650F 6BBB 563A BDA5 DD1C 82EC 27F6"
INCREMENT 64800INVPRO_F adskflex 1.000 permanent 2 \
VENDOR_STRING=commercial:permanent BORROW=4320 SUPERSEDE \
DUP_GROUP=UH SUITE_DUP_GROUP=UHV ISSUED=25-Jun-2008 \
SN=399-99999966 SIGN="0BE4 51F4 570C DC48 5E66 F952 629E EDF0
\
019C 6FF7 0509 1FF0 D4FB 3B16 1981 073F 31EC A241 8CB3 8782 \
E655 00C6 E097 D5EF B0D8 67D3 199D 699D 2E09 B16F" SIGN2="1254
\
3E37 0CE4 F42D B7CD 858C 92FC A963 5274 770F 9354 FE29 E117 \
205D C632 0C4E AEC0 7501 9D9E FFEB D84D F154 16A1 E120 339A \

```

FDBF 3F07 4477 B8B3 5DA4"

License Types and Behaviors

Autodesk supports dynamic product usage and license behaviors. This means that you can purchase a specific type of behavior with a specific license and change that license at a later date without having to uninstall and reinstall the Autodesk product.

NOTE All license types are available as stand-alone and network except for the Student Portfolio license, which is available as stand-alone only.

License types include the following:

- **Commercial.** A license for a product that was purchased commercially.
- **Not for Resale.** A license for a product that is not sold commercially. Not for Resale products are for evaluation or demonstration purposes only and may not be used for commercial or production use.
- **Educational (EDU)/Institution.** A license designed specifically for educational institutions.
- **Student Portfolio.** A license for students who are using an Autodesk product as part of their curriculum.

License behaviors are as follows:

- **Permanent.** Enables permanent use of an Autodesk product.
- **Term Extendable.** Enables access to an Autodesk product for a limited time. The term can be extended at any time.
- **Term Non-Extendable.** Enables an Autodesk product for a limited time. The term cannot be extended.

Heartbeat Signal

When an Autodesk product is running, it communicates with the license server at regular intervals using a communication method known as the "heartbeat" signal. If the heartbeat signal is lost, the server tries to reconnect. If the server cannot reconnect, the user receives a license error.

If the product stops working because it has lost a connection to the server, you must shut down the product, and then restart it. If the problem causing the original loss of the heartbeat signal is resolved and there are available licenses on the server, the program can be restarted.

Network License Manager

Install the Network License Manager

The Network License Manager is used to configure and manage license servers. It includes the `lmgrd`, `adskflex`, and `lmutil` tools that you need to set up your license server.

If an earlier version of the Network License Manager is already installed on the computer, you should upgrade by installing the Autodesk Network License Manager into the folder where the older version was located.

Install the Network License Manager (Windows)

You can install the Network License Manager before or after you use the Installation wizard. The order in which you install the network applications does not matter, as long as you install everything you need and you provide consistent license server information across the network applications.

To install your Network License Manager

- 1 In the Autodesk Installation wizard, click **Install Tools and Utilities**.
- 2 On the **Select the Products to Install** page, select **Autodesk Network License Manager** and click **Next**.
- 3 Review the Autodesk software license agreement for your country or region. You must accept this agreement to proceed with the installation. Choose your country or region, click **I Accept**, and then click **Next**.

NOTE If you do not agree to the terms of the license and want to terminate the installation, click **Cancel**.

- 4 On the **Begin Installation** page, review your product selection and the current settings. If you do not want to change anything, click **Install**. If you want to change the install type or installation path, click **Configure**.

- 5 On the Select the Installation Location page, accept the default installation path (*C:\Program Files\Autodesk Network License Manager*) or Browse to specify a different path. If you enter a path that does not exist, a new folder is created using the name and location you provide. Click Next.

WARNING Do not install the Network License Manager on a remote drive. When you install the Network License Manager files, you must provide a path to a local drive. You must specify the drive letter; the universal naming convention (UNC) is not permitted.

- 6 On the Configuration Complete page, click Configuration Complete to return to the confirmation page.
- 7 On the Begin Installation page, click Install.
- 8 When the Installation Complete page displays, click Finish.

If you have installed the Network License Manager on an IPv6 network, you must follow the instructions in [Patch the License Manager on an IPv6 Network](#) on page 60 to enable it.

Install the Network License Manager (Mac OS X)

To install the Network License Manager

- 1 Navigate to the NetworkLicenseManager folder on your Showcase DVD, or in the package you downloaded.
- 2 Do one of the following:
 - (DVD) Double-click the Network License Manager package icon.
 - (Download) Double-click the Network License Manager .dmg, then double-click the Network License Manager package icon.

The Install Autodesk NLM wizard appears.

- 3 Click Continue to begin the installation, then follow the instructions in the installer to install the Network License Manager tools.
- 4 Click Close when you see the Install Succeeded message.

By default, the Network License Manager tools are installed in the following directory: `/usr/local/flexnetserver`. In addition, scripts to help set up your license server are installed in the following directory: `/Library/StartupItems/adsknlm`.

If you have installed the Network License Manager on an IPv6 network, you must follow the instructions in [Patch the License Manager on an IPv6 Network](#) on page 60 to enable it.

Install the Network License Manager (Linux)

To install the Network License Manager

- 1 Open a shell as a super user.
- 2 Navigate to the NetworkLicenseManager directory on your Showcase DVD, or extract the Network License Manager package from the compressed file that you downloaded.
- 3 To install the Network License Manager, enter the following command:

```
rpm -ivh adlmflexnetserver-#.rpm
```

where # is the package number.

If you have installed the Network License Manager on an IPv6 network, you must follow the instructions in [Patch the License Manager on an IPv6 Network](#) on page 60 to enable it.

Patch the License Manager on an IPv6 Network

If you are using a license server on an IPv6 network, you must install a patch to the Autodesk Network License Manager, otherwise the license server will not work.

To install the patch on Windows:

- 1 Shut down your license server.
- 2 Back up the contents of the license manager files. By default, these are in *C:\Program Files\Autodesk Network License Manager*.
- 3 Download the patch from <http://www.autodesk.com/nlm2011-ipv6-windows>.
- 4 Unzip the patch and paste the new files over the old ones; these are located by default in *\Program Files\Autodesk Network License Manager*. (Four files will be overwritten.)
- 5 Restart your license server.

To install the patch on Linux and Mac:

NOTE Autodesk Network License Manager IPv6 is only supported on 64-bit platforms of Linux and 32-bit platforms of Mac OS X.

1 Open a Terminal window and navigate to the Autodesk Network License Manager folder (where *lmutil*, *lmgrd* and *adskflex* are installed).

2 Enter the following command to stop the license server:

```
./lmutil lmdown -c @hostname -q -all -force
```

If you do not know the host name, enter the following command in Terminal to locate the name of each server you plan to use:

```
lmutil lmhostid-hostname
```

3 Download the patch:

■ **Linux:** <http://www.autodesk.com/nlm2011-ipv6-linux>

■ **Mac:** <http://www.autodesk.com/nlm2011-ipv6-mac>

4 Do one of the following:

■ Double-click the archive file to extract it to the current folder; or,

■ Enter the following in Terminal:

Linux:

```
tar -zxvf nlmipv6support_linux64.tar.gz.
```

Mac:

```
tar -zxvf nlmipv6support_mac32.tar.gz.
```

5 Replace the original Autodesk Network License Manager file with the newly extracted file.

6 Navigate to the Autodesk Network License Manager folder once more.

7 Enter the following command to restart the Network License Manager:

```
./lmgrd -c license_file_list -I debug_log_path
```

Autodesk recommends starting *lmgrd* as a non-root user. If you must start *lmgrd* as a root user, enter the following to run *lmgrd* as a non-privileged user:

```
su username ./lmgrd -c license_file_list -I debug_log_path
```

where *username* is a non-privileged user.

Obtain a License Through autodesk.com

You can register and activate your network license by going to <https://registeronce.autodesk.com> and following the on-screen instructions.

Obtain the Server Host Name and Host ID Manually

Autodesk uses the server host name, host ID, and product serial number to generate a license file.

To obtain the information manually, you can use the command prompt or you can run the *lmtools.exe* utility. If you use *lmtools.exe*, do not run it on a remote workstation.

To obtain the host name and ID using the Windows command prompt

- 1 Do one of the following:
 - (Windows XP) Click Start > Programs > Accessories > Command Prompt.
 - (Windows Vista) Click Start > All Programs > Accessories > Command Prompt.
- 2 In the Windows command prompt, enter the following command, then press Enter:

```
ipconfig /all
```
- 3 Locate the Host Name line, and write down the host name.
- 4 Locate the Physical Address line. Write down the physical address without the dashes. This is your twelve-character host ID.

NOTE If your server has more than one network adapter, select the one that corresponds to a physical network adapter. To determine which adapters are physical: in the Windows command prompt, enter `ipconfig /all`, and then view the Description field above each physical address. If there is more than one physical network adapter, it does not matter which one you use. Devices such as VPN adapters, PPP adapters, and modems are not valid.

- 5 Close the Windows command prompt.

To obtain the host name and ID using *lmtools.exe*

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 2 In the LMTOOLS program, click the Systems Settings tab.
- 3 On the Systems Settings tab, locate the Computer/Hostname box. Copy the host name and paste the information into a text editor.
- 4 Locate the Ethernet Address box. The Ethernet address is the host ID. It consists of twelve characters. Write down the information. If your Ethernet address is more than twelve characters, write down the first twelve characters only.

NOTE If your server has more than one Ethernet adapter, select one that corresponds to a physical network adapter.

- 5 Close *lmtools.exe*.

To obtain the host name and ID using the Mac OS X or Linux terminal window

- 1 Launch a Terminal window.
- 2 Go to the directory where *lmutil* is installed.
- 3 Retrieve the host name by entering the following in Terminal:

```
<prompt>./lmutil lmhostid -hostname
```

The host name is displayed.
- 4 Retrieve the host ID by entering the following in Terminal:

```
<prompt>./lmutil lmhostid
```

The twelve-character host ID is displayed.
- 5 Close the Terminal Window.

Content reference to: **Configure a License Server (Windows)**

Configure a License Server

Configure a License Server (Linux)

You configure a license server so that you can manage your Autodesk product licenses.

To configure automatic start-up of your license server

Before configuring your license server for Linux, ensure that the following steps have been completed:

- You have installed the Autodesk Network License Manager which contains the following files: *lmgrd*, *adskflex*, and *lmutil*.
- You have received the network license file from Autodesk that contains the product licenses; for example, *productlicense.lic*.

- 1 Extract the FLEXnet IPv4 server files into the following directory:
/home/<user id>/flexlm11.7.

NOTE Replace *<user id>* with your user id, not a root user id.

- 2 Copy the *.lic* file into the *flexlm11.7* directory created in Step 1.
- 3 Open a terminal window in root mode.
- 4 Go to the directory */etc/*.
- 5 Locate the *rc.local* file.
- 6 Edit the *rc.local* file and start *lmgrd* by entering the following commands in the terminal window:

NOTE Replace *acad.lic* with your license file name.

- 7

```
/bin/su <user id> -c 'echo starting lmgrd'\  
/home/<user id>/flexlm11.7/boot.log'  
  
/usr/bin/nohup/bin/su <user id> -c 'umask 022;\  
/home/<user id>/flexlm11.7/lmgrd -c\
```

```
/home/<user id>/flexlm11.7/acad.lic >> \  
/home/<user id>/flexlm11.7/boot.log `  
/bin/su <user id> -c `echo sleep 5 >> \  
/home/<user id>/flexlm11.7/boot.log `  
/bin/sleep 5  
/bin/su <user id> -c `echo lmdiag >>\  
/home/<user id>/flexlm11.7/boot.log `  
/bin/su <user id> -c `/home/<user id>/flexlm11.7/lmutil lmdiag  
-n -c\  
/home/<user id>/flexlm11.7/acad.lic >> \  
/home/<user id>/flexlm11.7/boot.log `  
/bin/su <user id> -c `echo exiting >>\  
/home/<user id>/flexlm11.7/boot.log `
```

- 8 Save the edited *rc.local* file.
- 9 Reboot your machine and verify that the *lmgrd* and *adskflex* have started by doing one of the following:
 - During the reboot, look for the message that the license server has started.
 - Check the *boot.log* file created in */home/<user id>/flexlm11.7/* to see if *lmgrd* and *adskflex* have started.

NOTE Before performing any system maintenance on your license server, see [Stop and Restart the License Server](#) on page 68.

Install SAMreport-Lite (Optional)

SAMreport-Lite is a reporting tool that helps you track network license usage. With SAMreport-Lite technology from Acresto™ Software, you can monitor client usage for Autodesk network licensed products.

To learn more about installing and using SAMreport-Lite, see the *SAMreport-Lite User's Guide*.

Uninstall the Network License Manager

You can uninstall the Network License Manager from the license server. When you uninstall the Network License Manager, licenses are no longer available to your users.

NOTE You must manually delete files that you created for use with the Network License Manager (such as log files, license files, and the Options file). They are not automatically deleted when you uninstall.

Uninstall the Network License Manager (Windows)

To uninstall the Network License Manager

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 2 In the LMTOOLS program, click the Start/Stop/Reread tab.
- 3 On the Start/Stop/Reread tab, click Stop Server.
- 4 Close *lmtools.exe*.
- 5 In the Windows Control Panel, do one of the following:
 - (Windows XP) Double-click Add/Remove Programs.
 - (Windows 7/Windows Vista) Double-click Programs and Features.Do one of the following:
 - (Windows XP) In the Add/Remove Programs window, click Autodesk Network License Manager. Click Remove.
 - (Windows 7/Windows Vista) In the Programs and Features window, click Autodesk Network License Manager. Click Remove.
- 6 If prompted, restart your computer.

Uninstall the Network License Manager (Mac OS X)

To uninstall the Network License Manager

- 1 Delete the following directories:

- /usr/local/flexnetserver/
- /Library/StartUpItems/adsknlm

This removes the main license server tools as well as the configuration scripts that help you set up your license server.

- 2 Reboot your machine.

Uninstall the Network License Manager (Linux)

To uninstall the Network License Manager

- 1 Open a shell as a super user.
- 2 Execute the following command to verify the package number of the Network License Manager that you installed:

```
rpm -qa |grep adlm
```

- 3 Execute the following command to uninstall the Network License Manager package:

```
rpm -e adlmflexnetserver-#.rpm
```

where # is the package number.

- 4 If you edited your rc.local file to configure your license server (for example to start lmgrd), remove those commands from the rc.local file.
(See also [Configure a License Server \(Linux\)](#) on page 64.)

Network License Tools

Autodesk Network licensing tools include FLEXnet configuration tools, license borrowing, and SAMreport-Lite. Each tool is described in the sections that follow.

This section also includes information for updating FLEXnet and installing and configuring the Autodesk Network License Manager on a network.

FLEXnet Configuration Tools

The Network License Manager uses FLEXnet® license management technology from Acreso Software. FLEXnet provides administrative tools that help to simplify management of network licenses. You can use FLEXnet tools to monitor network license status, reset licenses lost to a system failure, troubleshoot license servers, and update existing license files on the fly.

For specific information about using FLEXnet configuration tools, you can find the `LicenseAdministration.pdf` document in the following directory:

- (Windows) `C:\Program Files\Autodesk Network License Manager\Docs\FlexUser\LicenseAdministration.pdf`

Utilities for License Server Management

FLEXnet provides two utilities for managing the license server. These tools are located in the `C:\Program Files\Autodesk Network License Manager` folder.

lmtools.exe Provides a Microsoft® Windows graphical user interface for managing the license server.

lmutil.exe Provides a set of command line options for managing the license server.

You can use `lmtools.exe` or `lmutil.exe` to perform the following server management tasks:

- Start, stop, and restart the server.
- Configure, update, and reread the license file.
- Diagnose system or license problems.
- View server status, including active license status.

Stop and Restart the License Server

Before you can perform any system maintenance on your license server, you must stop the license server. When you have completed maintenance, you can restart the license server.

To stop the license server (Windows)

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 2 In the LMTOOLS program, on the Service/License File tab, select the Configure Using Services option.
- 3 Select the service name for the license server you want to stop manually.
- 4 Click the Start/Stop/Reread tab.
- 5 On the Start/Stop/Reread tab, click Stop Server.
- 6 Close *lmtools.exe*.

To restart the license server (Windows)

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 2 In the LMTOOLS program, on the Service/License File tab, select the Configure Using Services option.
- 3 Select the service name for the license server you want to start manually.
- 4 Click the Start/Stop/Reread tab.
- 5 On the Start/Stop/Reread tab, click Start Server to restart the license server.

To stop the license server (Mac OS X)

Enter the following in Terminal:

```
sudo /sbin/SystemStarter stop adsknlm
```

To restart the license server (Mac OS X)

Enter the following in Terminal:

```
sudo /sbin/SystemStarter restart adsknlm
```

To stop the license server (Linux)

Enter the following in Terminal:

```
./lmutil lmdown -q -force
```

To restart the license server (Linux)

Enter the following in Terminal:

```
./lmgrd -c acad.lic -l debug.log
```

NOTE Replace *acad.lic* with your license file name and *debug.log* with your log file name.

Update FLEXnet from a Previous Version

This release of Autodesk products and later require FLEXnet version 11.7.0.0 or later. If you are currently using a version of FLEXnet that is earlier than 11.7.0.0, you need to upgrade to version 11.7.0.0 or later.

NOTE If the server where you plan to install the Autodesk Network License Manager has FLEXnet installed for another product, make sure that the version of *lmgrd.exe* is the most current version.

To determine what version of FLEXnet is installed, you need to verify the version of the following files:

Windows

- *lmgrd.exe*
- *lmtools.exe*
- *lmutil.exe*
- *adskflex.exe*

Mac OS X or Linux

- *lmgrd*
- *lmutil*
- *adskflex*

To verify the version of *lmutil.exe*, *lmtools.exe*, or *adskflex.exe* (Windows)

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 2 In *lmtools.exe*, click the Utilities tab.
- 3 On the Utilities tab, enter the location of the file, or click the Browse button to locate the file and click Open. The file location should look something like this:
C:\Program Files\Autodesk Network License Manager\lmutil.exe
- 4 On the Utilities tab, click Find Version.
The version number of the file you selected is displayed. If necessary, use the following procedure to update your version of FLEXnet.

To verify the version of *lmutil*, *lmgrd*, or *adskflex* (Mac OS X or Linux)

You should be logged in with the same user ID you used when installing the FLEXnet files, for example, */Users/<userid>/adsknlm* (Mac OS X) or */home/<userid>/adsknlm* (Linux).

Enter the following commands in the terminal window/prompt:

```
<prompt>./lmutil -v
<prompt>./lmgrd -v
<prompt>./adskflex -v
```

The output of each command will look similar to this example:

```
Copyright © 1989-2007 Macrovision Europe Ltd. And/or Macrovision
Corporation. All Rights reserved.
lmutil v11.5.0.0 build 56285 i86_mac10
```

To update FLEXnet (Windows)

You should be logged in with Administrator rights when working with the LMTOOLS utility.

- 1 Back up your license files.
- 2 Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
- 3 In the LMTOOLS program, click the Start/Stop/Reread tab.

- 4 On the Start/Stop/Reread tab, click Stop Server.
- 5 Close *lmtools.exe*.
- 6 Note the location where the Network License Manager is installed and then uninstall the Network License Manager. For details about uninstalling the Network License Manager, see Uninstall the Network License Manager.
- 7 Install the Network License Manager. For details about installing the Network License Manager to the same location as the previous version, see Install the Network License Manager.
- 8 Do one of the following:
 - (Windows XP) Click Start ► Programs ► Autodesk ► Network License Manager ► LMTOOLS.
 - (Windows Vista) Double-click the LMTOOLS icon on the desktop.
- 9 In the LMTOOLS program, click the Start/Stop/Reread tab.
- 10 On the Start/Stop/Reread tab, click Start Server.
- 11 Close *lmtools.exe*.

To update FLEXnet (Mac OS X)

You should be logged in with the same user ID you used when installing the FLEXnet files, for example, */Users/<userid>/adsknlm*. The logged in user ID should be in the *sudoers* list to execute some of the following commands.

- 1 Back up your license files.
- 2 Stop the Autodesk Network License Manager service by entering the following in Terminal:


```
sudo /sbin/SystemStarter stop adsknlm
```
- 3 Note the location where the Network License Manager is installed and then uninstall the Network License Manager by entering the standard Mac OS X commands, for example, *rm*.
- 4 Install the Network License Manager. Copy the new version of the FLEXnet network license manager files (*lmgrd*, *adskflex*, and *lmutil*) to the location recommended when you configured your license server, for example, */Users/<user id>/adsknlm*.
- 5 Start the Autodesk Network License Manager service by entering the following in Terminal:

```
sudo /sbin/SystemStarter start adsknlm
```

NOTE Version 11.7.0.0 of the FLEXnet license manager that ships with Autodesk products is backwards compatible and will administer licenses for the Autodesk 2008-, 2007-, 2006-, 2005-, 2004-, and 2002-based products.

To update FLEXnet (Linux)

You should be logged in with the same user ID you used when installing the FLEXnet files, for example, `/home/<userid>/adsknlm`. The logged in user ID should be in the *sudoers* list to execute some of the following commands.

1 Back up your license files.

2 Stop the Autodesk Network License Manager service by entering the following in Terminal:

```
./lmutil lmdown -q -force
```

3 Note the location where the Network License Manager is installed and then uninstall the Network License Manager by entering the standard Linux commands, for example, *rm*.

4 Install the Network License Manager. Copy the new version of the FLEXnet network license manager files (*lmgrd*, *adskflex*, and *lmutil*) to the location recommended when you configured your license server, for example, `/home/<user id>/adsknlm`.

5 Start the Autodesk Network License Manager service by entering the following in Terminal:

```
./lmgrd -c acad.lic -l debug.log
```

NOTE Replace *acad.lic* and *debug.log* with your license file name and log file name.

NOTE Version 11.7.0.0 of the FLEXnet license manager that ships with Autodesk products is backwards compatible and will administer licenses for the Autodesk 2008-, 2007-, 2006-, 2005-, 2004-, and 2002-based products.

Set Up and Use an Options File

With an Options file, you set configuration options for managing licenses on each license server that you set up. An Options file sets parameters that the license file reads and the `lmgrd` program executes.

If you want to have the same license behavior on some or all of your license servers, you must save the same Options file to each of those license servers. If you want to specify different license behavior on different license servers, you must create an Options file for each license behavior. You must save each Options file to the server where you want specific license behavior.

NOTE For Options file changes to take effect on a license server, you must save the Options file, and then use `lmtools.exe` to reread the license file.

Use the Options file to set parameters for the following server-related features:

Report log file A compressed, encrypted file is created that generates accurate usage reports on license activity for use by SAMreport-Lite. See [Create a Report Log](#) on page 75.

License borrowing If your Autodesk product supports the license borrowing feature, you can allow users to borrow an Autodesk product license from a network license server so that they can use the product without being connected to the license server. A license can be borrowed for a limited time. See [Configure License Borrowing with the Options File](#) on page 76.

License timeout With license timeout, you can set a timeout period on your license server for one Autodesk product at a time. When set, license timeout returns a license to the license server when a connection with the workstation is lost, or if a license is checked out but the Autodesk product is idle on a workstation for longer than the timeout period you define. See [Set Up License Timeout](#) on page 77.

License timeoutall With license timeoutall, you can set a timeout period on your license server that applies to all Autodesk products installed on your computer. When set, license timeout returns a license to the license server when a connection with the workstation is lost, or if a license is checked out but the Autodesk product is idle on a workstation for longer than the timeout period you define. See [Set Up License Timeout](#) on page 77.

Here is an example of the contents of an Options file:

```
REPORTLOG=c:\test\report.rl  
  
BORROW_LOWWATER Autodesk_f1 3
```

TIMEOUT Autodesk_f1 7200

You can also set up advanced license parameters, such as reserving a license, restricting license usage, or defining groups of users. To learn more about setting advanced Options file parameters, see the FLEXnet documentation in the *C:\Program Files\Autodesk Network License Manager\LicenseAdministration.pdf* file.

Create an Options file

You should be logged in with Administrator rights when working with the LMTOOLS utility.

To create an options file

- 1 Open a text editor, enter the parameters you want, and then save the document as a file named *adskflex.opt* to the same location where you saved the license file.

NOTE Make sure you save the file with the extension *.opt*. The default extension *.txt* is not recognized by the Network License Manager.

- 2 Do one of the following:
 - (Windows) Click Start ► All Programs ► Autodesk ► Network License Manager ► LMTOOLS Utility.
 - (Mac OS X) Launch a Terminal window, navigate to the Autodesk Network License Manager folder, and enter the following:

```
./lmutil lmreread -c @hostname-all
```

Close the Terminal window.
- 3 In the LMTOOLS program, on the Start/Stop/Reread tab.
- 4 On the Start/Stop/Reread tab, click ReRead License File.
- 5 Close *lmtools.exe*.

Create a Report Log

In the Options file, you can create a report log file that is used with SAMreport-Lite.

To create a report log

- 1 In a text editor, open the Options file, *adskflex.opt*.
- 2 In the Options file, enter the following syntax on its own line (with REPORTLOG entered in uppercase, as shown):

REPORTLOG [+]*report_log_path*

For example (Windows), the syntax REPORTLOG +"c:\My Documents\report.rl" means that a report log named *report.rl* is located in the folder *c:\My Documents*.

For example (Mac OS X or Linux), the syntax REPORTLOG +"/Users/<user id>/NLM/report.rl" means that a report log named *report.rl* is located in the folder */Users/<user id>/NLM*.

NOTE Path names that contain spaces must be enclosed in quotation marks.

In the REPORTLOG syntax, "[+]" means that entries to the log file you create are appended rather than replaced each time the Network License Manager is restarted. (It is recommended that you use this option so that you retain a history of log entries.)

Configure License Borrowing with the Options File

If your Autodesk product supports the license borrowing feature, you can use the Options file to configure license borrowing options. For example, you can define the maximum number of licenses that cannot be borrowed from your network at any one time. In addition, you can define which users can borrow an Autodesk product license. Licenses are borrowed per user, not per machine.

NOTE If your Autodesk product supports license borrowing, and licenses are borrowed from a redundant license server pool, you must restart the license server after you stop the Network License Manager.

At the end of a borrow period, the borrowed license is automatically disabled on the user's computer and becomes available again on the license server. Users can also return a license before a borrow period has ended.

To set license borrowing parameters

- 1 In the Options file, enter the following syntax on its own line (with BORROW_LOWWATER entered in uppercase, as shown):

BORROW_LOWWATER *feature_code n*

In the BORROW syntax, “feature_code” is the name of the product in the license file, and “n” is the number of licenses that cannot be borrowed.

For example, the syntax BORROW_LOWWATER Autodesk_f1 3 means that for the product Autodesk_f1, three licenses cannot be borrowed from the license server.

- 2 Enter the following syntax on the next line (with MAX_BORROW_HOURS entered in uppercase, as shown):

MAX_BORROW_HOURS feature_code n

In this syntax, “n” is the number of hours that a license can be borrowed.

For example, the syntax MAX_BORROW_HOURS Autodesk_f1 360 means that for product Autodesk_f1, licenses can be borrowed for 360 hours, or 15 days.

NOTE Licenses are borrowed in increments of 24 hours only. Any number that is more than a 24-hour increment is not used. For example, the number 365 would be rounded down to 360 hours, or 15 days.

For more information about setting up the license borrowing feature, see the FLEXnet documentation in the *C:\Program Files\Autodesk Network License Manager* folder.

NOTE To borrow a license in an Autodesk product, click Help menu ► About ► Product Information. Alternatively, enter **borrowlicense** on the product command line. Help for this feature is available in the Borrow a License for [Autodesk Product] window and in *C:\Program Files\[Autodesk Product]\Help\adsk_brw.chm*.

Set Up License Timeout

License timeout is set in the Options file to determine how long a product session can be idle before the license is reclaimed by the license server. When you set this flag in the Options file, a user's license is reclaimed by the license server if the product is idle on a workstation for more than the timeout period you define.

If a user's license is lost because of the idle timeout, the product attempts to claim a new license once the user uses the product again. If no license is available, the user can save work before the product shuts down.

You can set individual license timeouts for each Autodesk product on your computer by using the TIMEOUT parameter or you can set one license timeout

for all Autodesk products on your computer by using the `TIMEOUTALL` parameter.

To set license timeout parameters

- For individual Autodesk products: In the Options file, enter the following syntax on its own line (with `TIMEOUT` entered in uppercase, as shown):
`TIMEOUT feature_code n`

In the `TIMEOUT` syntax, “feature_code” is the name of the product (referred to in the `INCREMENT` line in the license file), and “n” is the number of seconds before an inactive license is reclaimed by the license server.

For example, the syntax `TIMEOUT Autodesk_f1 7200` means that for the product `Autodesk_f1`, the license timeout period is set for 7200 seconds, or two hours.

- For all Autodesk products: In the Options file, enter the following syntax on its own line (with `TIMEOUTALL` entered in uppercase, as shown):
`TIMEOUTALL n`

In the `TIMEOUTALL` syntax, “n” is the number of seconds before an inactive license is reclaimed by the license server.

For example, the syntax `TIMEOUTALL 7200` means that for all Autodesk products, the license timeout period is set for 7200 seconds, or two hours.

For more information about using the license timeout feature, see the FLEXnet documentation in the `C:\Program Files\Autodesk Network License Manager` folder.

License Borrowing

If you are running a network-licensed version of the program, you can borrow a license from a license server to use the program for a specified time when your computer is not connected to the network.

Overview

If you are using a network-licensed version of your Autodesk product and your network administrator supports the license borrowing feature, you can borrow a product license from your network license server to use the program when your computer is not connected to the network. Your license is automatically

returned to the license server at the end of the day on the return date you set when you borrowed the license. You can also return a license early.

NOTE There is a limit to the number of licenses available for borrowing. If you try to borrow a license and are notified that no licenses are available, all network licenses may already be borrowed by other users. If you are unable to borrow a license, see your network administrator for help.

If you have a stand-alone version of the program, you cannot borrow a license. You can, however, use the License Transfer Utility to transfer your license from one computer to another. To check your license type, select Help > About Showcase from the main menu bar and click Product License Information to open the dialog box.

Borrow a License

You can run the program when your computer is not connected to the network until your license-borrowing period ends. If you don't remember the date that a license expires, you can check the date by selecting Help > About Showcase and clicking Product License Information. This opens the Product License Information dialog box.

When the license-borrowing period expires, the borrowed license is automatically returned to the license server. Once your computer is reconnected to the network, you can run the program from the network or borrow a license again.

Interaction with Other License-Borrowing Tools

Using the license borrowing feature in the program is the recommended way to borrow a license; however, some third-party borrowing tools may also be available to you. These tools are not supported or compatible with the license borrowing feature in the program. Other third-party or legacy license-borrowing tools that may be available to you are the Autodesk License Borrowing utility (shipped with Autodesk products) and the borrowing feature in *lmtools.exe*, a component of the Autodesk Network License Manager.

If another license-borrowing tool is active when you attempt to use the license borrowing feature, you should proceed as follows to borrow a license for the program:

- If you run the Autodesk License Borrowing utility that shipped with your Autodesk product and then turn on the borrowing flag for the Adskflex option or the All option, a license can be borrowed when you start the

program. However, you cannot return a license until you exit and then restart the program.

- If borrowing is set in *lmtools.exe* for *all* products, you can either (a) use the other tool to borrow licenses for the program or (b) stop the borrowing process in *lmtools.exe* and then use the license borrowing feature in the program.
- If borrowing is set in *lmtools.exe* for non-Autodesk products only, you must stop the borrowing process in *lmtools.exe*. You can then use the license borrowing feature to borrow licenses for your Autodesk product. If you do not stop the borrowing process in *lmtools.exe*, the license borrowing feature will not function.

To borrow a license using the Help menu

- 1 Select Help > About Showcase.
- 2 In the About Showcase window, click Product License Information.
- 3 In the Product License Information window, click Borrow License.
- 4 In the Borrow a License window, on the calendar, click the date when you want to return the license.
This date must be within the valid date range set by your network administrator. The valid date range is displayed in this window.
- 5 Click Borrow License.
- 6 In the License Borrowed message, click OK.
The license is borrowed, and you can now use the program while your computer is disconnected from the network.

Borrow a License window

Using the license borrowing feature, you can borrow a license from your network license server, and then use the license when your computer is disconnected from the license server; for example, when you are traveling for work.

The Borrow a License window has the following options:

Calendar Sets the date when you plan to return a borrowed license. The return date must be within the range specified by your network administrator.

Borrow a License Borrows the license from the network license server based on the return date that you specified.

Cancel Cancels the borrowing action; no license is borrowed.

Return a license

Your network license is automatically returned to the network license server on the day that the license expires. You can also return a license earlier than the date you originally selected, as long as your computer is connected to the network license server when you attempt to return the borrowed license.

Once a borrowed license is returned, you can borrow a license again as long as your computer is connected to the network license server and a license is available on the server.

To return a borrowed license early

- 1 Select Help > About Showcase, then click Product License Information.
- 2 In the Product License Information window, click Return License, then click Yes.

Your license is returned to the network license server. After you return the borrowed license, you can borrow a license again immediately as long as a license for that product is available on the network.

To check the license return date

- 1 Select Help > About Showcase, then click Product License Information.
- 2 In the Product License Information window, under License Expiration Date, view the license return date.

Network Licensing FAQs

What is the difference between a stand-alone license and a network license?

Stand-alone licensed products are registered and activated to an individual workstation. While the software can be installed on multiple systems in your facility, the license only allows one system to be operational. If you need to

run more systems, you need to purchase more stand-alone licensed products, or consider converting to network licenses.

Network licensed products rely on the Network License Manager to keep track of software licenses. The software can be installed and run on multiple systems, up to the maximum number of licenses you've purchased. The Network License Manager "checks out" licenses until they are all in use. No further systems can run the program until a license is "checked in." If you need to run more systems, you can purchase additional licenses for the Network License Manager to maintain.

What is the benefit of using a network licensed version of the software?

Network licensed products are recommended for large drafting/design facilities, classrooms, and lab environments. The main advantage is that you can install products on more systems than the number of licenses you have purchased (for example, purchasing 25 licenses but installing on 40 workstations). At any one time, products will run on the maximum number of systems for which you have licenses. This means you get a true floating license. If software needs to be run on more systems, additional licenses can be purchased.

Registration and activation occurs only once and the licenses are maintained on your network license server.

How do I switch my license from stand-alone to network or network to stand-alone?

If you have purchased stand-alone and network licenses and you want to switch which license Showcase is using, there are two main methods to change the license type.

- Uninstall and re-install Showcase, changing the type of license you specify during the install.
- Edit the `SHOWCASE_LICENSE_METHOD` environment variable in your `license.env` file.
If you have added the `SHOWCASE_LICENSE_METHOD` variable to your system environment variables or to a `Showcase.env` file, you must also update the license type in those locations.

To edit the SHOWCASE_LICENSE_METHOD environment variable

- 1 Locate the `license.env` file in the following location:
 - (Windows) `C:\Program Files\Autodesk\Showcase2011\bin`
- 2 Edit the `SHOWCASE_LICENSE_METHOD` variable to indicate the type of license you want, for example:

```
SHOWCASE_LICENSE_METHOD=standalone
```

to set Showcase to use a stand-alone license, or

```
SHOWCASE_LICENSE_METHOD=network
```

to set Showcase to use a network license.

If you are switching from a stand-alone to a network license, continue with the following steps to set your license server name.
- 3 Navigate to the following directory to locate and open the `LICPATH.LIC` file.
 - (Windows) `C:\Program Files\Autodesk\Showcase2011`
- 4 Edit the line `SERVER <servername>` where `<servername>` is your license server name.

If you do not find the `LICPATH.LIC` file in this location, you can create a license file by saving a text file with the extension `.lic`, and including the following lines:

```
SERVER <servername> 0
USE_SERVER
```

IMPORTANT If you have added the `SHOWCASE_LICENSE_METHOD` variable to your system environment variables or to a `Showcase.env` file, you must also update the license type in those locations.

The `Showcase.env` file is found in `C:\Documents and Settings\user\My Documents\showcase`.

To locate the Showcase.env file

- Go to `C:\Documents and Settings\user\My Documents\showcase`

To set the variable in the environment

- From the Control Panel, double-click System to open the System Properties, then switch to the Advanced tab and click Environment Variables.

How do I change the license server information I entered during the installation?

To change the license server information you entered

- 1 Navigate to the following directory to locate and open the LICPATH.LIC file.

■ C:\Program Files\Autodesk\Showcase2011

- 2 Edit the line `SERVER <servername>` where `<servername>` is your license server name.

If you do not find the LICPATH.LIC file in this location, you can create a license file by saving a text file with the extension .lic, and including the following lines:

```
SERVER <servername> 0  
USE_SERVER
```

What is Internet Explorer used for?

After installing your product, you can operate in trial mode for a given number of days. Whenever you launch the program, you are prompted to activate the software. When you choose to activate the software, Internet Explorer makes this process much faster. Once you entered your registration data and submit it to Autodesk, an activation code is returned and you are not prompted again during startup.

Where can I find more information on troubleshooting network licensing?

If you experience difficulty with installation or licensing, visit <http://autodesk.com/servicesandsupport> for additional FAQ information, as well as an in-depth Knowledge Base that you can search for solutions to common installation and licensing issues and error messages.

Glossary of Licensing Terms

6

Glossary

ADSKFLEX_LICENSE_FILE In a distributed license server configuration, the environment variable used to point a workstation to the distributed license servers.

adskflex.exe The Autodesk vendor daemon used with the FLEXnet license technology. This daemon keeps track of the Autodesk licenses that are checked out and the workstations that are using the licenses.

borrowed license A license that allows you to use an Autodesk product for a limited period of time without having to buy a separate license or have network access to the license server.

daemon A program that runs continuously in the background of a computer. The daemon handles requests from the computer and then forwards the requests to other programs or processes. The Network License Manager uses two daemons: the vendor daemon (*adskflex.exe*) and the license manager daemon (*lmgrd.exe*).

debug log file A file used with FLEXnet to log connection activity (such as license failure or starting and stopping) between the Network License Manager and the workstation.

deployment The files and folders created on a server and used by workstations to install Autodesk programs.

distributed server A license server configuration option in which several servers are used to manage license distribution. Each distributed license server has a unique license file and a fixed number of licenses. If one distributed license server fails, the other servers are still able to distribute their licenses.

Ethernet address See *host ID*.

feature code A license file parameter that represents the product that is supported by that license file.

FLEXnet The Acresto Software license management technology implemented in the Autodesk family of products.

heartbeat signal The communication signal between the Network License Manager and the workstation to verify that the workstation is accessible and has an active Autodesk product session running.

host ID The unique hardware address of a network adapter. Also known as *Ethernet address* or *physical address*.

host name The TCP/IP name associated with a computer. FLEXnet technology uses the host name as a parameter; the host name must be distinguished from the NetBIOS (server) name.

idle A state of inactivity in your product that prompts a network license server to reclaim a license. Inactivity is due to no mouse or keyboard activity and no commands, LISP expressions, menu macros, or scripts in progress for the period of time that is defined in the Options file. See also *license timeout*.

JRE (Java Runtime Environment) A program that is required to run Java programs. This program must be installed with SAMreport-Lite.

license file A file used with FLEXnet that controls the number of available seats. This file must be in ASCII plain text format.

license server A server that contains the Network License Manager.

license timeout A feature that allows you to set up a timeout period on your license server to automatically return an idle license to the server so that it is available for use again.

licpath.lic In both single and redundant server configurations, the file used to point the workstation to the FLEXnet license server. *Licpath.lic* is located in the root installation folder.

lmgrd.exe The license manager daemon. This daemon handles the original contact with the program, and then passes the connection to the vendor daemon, *adskflex.exe*.

lmttools.exe A graphical user interface utility used to administer the FLEXnet license technology. (*Lmutil.exe* is the command line version of this utility.)

lmutil.exe A command line utility used to administer the FLEXnet license technology. (*Lmtools.exe* is the graphical user interface version of this utility.)

master daemon See *lmgrd.exe*.

network license installation A type of installation that requires you to install and run the Network License Manager from a network server. You must install and configure the Network License Manager before clients can run the Autodesk product.

Network License Manager The technology used by Autodesk for network license management.

Options file The file used by FLEXnet to control license manager parameters, such as reserving licenses and creating report logs used with SAMreport-Lite.

physical address See *host ID*.

redundant server A license server configuration option in which three servers are used to administer licenses. The redundant servers share a license file and a pool of licenses. The redundant server pool remains functional as long as two of the three servers are running and communicating with each other.

report log file A file used with FLEXnet and SAMreport-Lite. This log file provides information about network license usage. The Options file creates the report log.

SAMreport-Lite A version of Acreoso Software's SAMreport tool. SAMreport-Lite is included on the Autodesk product discs.

vendor daemon See *adskflex.exe*.

workstation A desktop computer used by an individual user on a network.

Index

A

- activating programs 14, 28, 33
- activation code 27
- administrative images
 - defined 18
- administrator permission requirements
 - stand-alone installation 8
- Adskflex option 79
- adskflex.exe (Autodesk vendor daemon) 46, 70
- anti-virus software 9
- applications
 - anti-virus software 9
 - closing during installation 9
 - uninstalling 15, 19
- Autodesk License Borrowing utility 79
- Autodesk Network License Manager 79
- Autodesk products
 - activating 28
 - borrowing network licenses for License Transfer utility 31 78
 - reinstalling 35
 - using off network 78
- Autodesk vendor daemon 70

B

- borrowing licenses
 - about 78
 - configuring 76
 - reconnecting and borrowing again 79, 81
 - returning licenses 81
- browsers 7
- bundled products 13

C

- Commercial licenses 28, 57

- computers 7
 - licenses for 31
- configuring
 - license borrowing 76
 - license servers 64, 74
- copying
 - licenses 31, 35

D

- daemons
 - license manager daemons 46
 - vendor daemons 46
 - versions of 70
- data loss 9
- dates
 - system dates 36
- Deployment wizard 36
- distributed license server model
 - about 44
 - license file example 50
- distributing
 - software installation images 36

E

- early returns of licenses 81
- Educational (EDU)/Institution
 - licenses 29, 57
- email registration 14
- Ethernet address 62
- exporting licenses
 - about 31
 - transfer files 32

F

- faxing registration information 14
- files
 - uninstalling 15

- FLEXnet tools
 - about 68
 - Options file 74–76
 - updating 70

G

- glossary 23, 87

H

- hard disks
 - system requirements 7
- hardware
 - installation requirements 7
 - license errors and 35
- hardware requirements
 - Network License Manager 39, 41–42
- heartbeat signals 57
- host IDs 62
- host names 62

I

- importing licenses
 - about 31
 - transfer files 33
- Imtools.exe 79
- install
 - Showcase on Windows (Quick Start) 4
- installation
 - License Transfer utility 32
 - multiple or bundled products 13
 - Network License Manager 58
 - networking issues 18
 - overview 3
 - preparing for 7
 - registration and activation 14
 - reinstalling 19
 - repairing damaged installations 19
 - SAMreport-Lite 65
 - serial numbers 8
 - starting 15

- system requirements 7
- troubleshooting 16
- uninstalling 15, 19
- workflow 3

Internet

- program registration and activation 14

- Internet Explorer (Microsoft) 7

L

- license borrowing
 - about 78
 - borrowing licenses 78
 - configuring 76
 - returning licenses 81
 - third-party licensing tools 79
- license files
 - about 47
 - combined products 51
 - package examples 52
- license manager daemon 46, 70
- license servers
 - borrowing licenses 78–79
 - configuring 64, 74
 - heartbeat signals 57
 - host IDs and host names 62
 - limited number of licenses 79
 - management utilities 68
 - models 43
 - returning licenses 81
 - stopping and restarting 68
 - third-party licensing tools 79
 - types of 43
- license timeout 77
- License Transfer utility
 - about 31
 - installing 32
 - transferring licenses 31
- licenses
 - about 45
 - active 31
 - assigning 45
 - availability 45
 - behaviors (term limits) 57, 74
 - copying 35

- exporting 32
- FLEXnet tools 68
- glossary 87
- importing 33
- license files 47
- license servers 64
- license timeout 77
- license types 17
- moving between computers 35
- single-user 27
- transferring 31, 33
- types of 57
- limits on number of licenses 79
- Linux
 - configuring license servers 64
 - Network License Manager 42
- lmgrd.exe (license manager daemon) 46, 70
- lmtools.exe utility 62, 68, 70
- lmutil.exe utility 68, 70
- log files
 - report log files 75

M

- Mac OS X
 - Network License Manager 41
- mailing registration information 14
- maintenance issues 19
- memory (RAM)
 - system requirements 7
- Microsoft Installer files (MSI) 18
- Microsoft Internet Explorer 7
- Microsoft Windows
 - Network License Manager 39
- Microsoft Windows operating systems 7
- monitors 7
- MSI files 18
- multi-product bundles 13

N

- network installations
 - issues 18
- network license installations
 - license behaviors 74

- license borrowing 76
- license timeout 77
- planning 39
- tools and utilities 67
- types of 57
- Network License Manager
 - assigning licenses 45
 - glossary 87
 - installing 58
 - license server models 43
 - uninstalling 66
 - upgrading 58
- network license servers
 - borrowing licenses 78–79
 - limited number of licenses 79
 - returning licenses 81
 - third-party licensing tools 79
- Not for Resale licenses 28, 57

O

- operating systems
 - reinstalling 35
 - system requirements 7
- Options file (FLEXnet tools) 74–76
- OS X
 - Network License Manager 41

P

- package license files 52–55
- Permanent licenses 29, 57
- permanent transfers of licenses 31
- permission requirements
 - stand-alone installation 8
- physical address 62
- pointing devices
 - system requirements 7
- private licenses 32
- processors 7
- Product Activation wizard 14, 27
- product information
 - viewing 29
- product keys 8, 14
- public licenses 32

Q

Quick Start
Windows install 4

R

RAM
system requirements 7
reactivating programs 35
redundant license server model
about 44
license file example 50
package license files 54
registering programs 14, 28
reinstalling
operating systems 35
removing
uninstalling programs 15, 19
repairing
damaged installations 19
report log files 75
restoring
damaged installations 19
returning borrowed licenses 79, 81

S

SAMreport-Lite
installing 65
serial number
updating 30
serial numbers
stand-alone installation 8
servers 18
host IDs and host names 62
license servers 64
stopping and restarting 68
service packs 7
single license server model
about 43
license file example 50
package license files 53
single-user licenses 27
software installation requirements 7

software requirements
Network License Manager 39, 41–42
stand-alone installations
program registration and activation 14
stand-alone licenses 27
Student Portfolio licenses 29, 57
system dates 36
system requirements
Network License Manager 39, 41–42
Showcase 7
stand-alone installations 7
system times 36

T

TCP/IP names 62
temporary transfers of licenses 31
Term Extendable licenses 29, 57
Term Non-Extendable licenses 29, 57
text editors 17
third-party licensing tools 79
time
system time 36
timeouts 77
transfer files
exporting 32
importing 33
transferring licenses 31
Trial licenses 29
trial mode 14
troubleshooting installation 16

U

uninstalling
Network License Manager 66
uninstalling programs 15, 19
updating
FLEXnet tools 70
upgrading
Network License Manager 58

V

vendor daemons 46, 70
video cards 7, 16
video monitors 7
virus software 9

W

web browsers 7
Windows
 install Showcase (Quick Start) 4
 Network License Manager 39
Windows operating systems
 system requirements 7

